

Network Working Group  
Request for Comments: 3332  
Category: Standards Track

G. Sidebottom  
Signatus Technologies  
K. Morneault  
Cisco  
J. Pastor-Balbas  
Ericsson  
Editors  
September 2002

## Signaling System 7 (SS7) Message Transfer Part 3 (MTP3) - User Adaptation Layer (M3UA)

### Status of this Memo

This document specifies an Internet standards track protocol for the Internet community, and requests discussion and suggestions for improvements. Please refer to the current edition of the "Internet Official Protocol Standards" (STD 1) for the standardization state and status of this protocol. Distribution of this memo is unlimited.

### Copyright Notice

Copyright (C) The Internet Society (2002). All Rights Reserved.

### Abstract

This memo defines a protocol for supporting the transport of any SS7 MTP3-User signalling (e.g., ISUP and SCCP messages) over IP using the services of the Stream Control Transmission Protocol. Also, provision is made for protocol elements that enable a seamless operation of the MTP3-User peers in the SS7 and IP domains. This protocol would be used between a Signalling Gateway (SG) and a Media Gateway Controller (MGC) or IP-resident Database, or between two IP-based applications. It is assumed that the SG receives SS7 signalling over a standard SS7 interface using the SS7 Message Transfer Part (MTP) to provide transport.

### Table of Contents

1. Introduction.....	3
1.1 Scope.....	3
1.2 Terminology.....	4
1.3 M3UA Overview.....	6
1.4 Functional Areas.....	10
1.5 Sample Configurations.....	18
1.6 Definition of M3UA Boundaries.....	21
2. Conventions.....	25

3.	M3UA Protocol Elements.....	25
3.1	Common Message Header.....	26
3.2	Variable Length Parameter.....	29
3.3	Transfer Messages.....	31
3.4	SS7 Signalling Network Management (SSNM) Messages.....	35
3.5	ASP State Maintenance (ASPSM) Messages.....	45
3.6	Routing Key Management (RKM) Messages.....	48
3.7	ASP Traffic Maintenance (ASPTM) Messages.....	59
3.8	Management (MGMT) Messages.....	63
4.	Procedures.....	69
4.1	Procedures to Support the M3UA-User .....	69
4.2	Procedures to Support the Management of SCTP Associations ...	70
4.3	AS and ASP State Maintenance.....	72
4.4	Routing Key Management Procedures.....	87
4.5	Procedures to Support the Availability or Congestion Status of SS7 Destination.....	89
4.6	MTP3 Restart.....	92
5.	Examples of M3UA Procedures.....	93
5.1	Establishment of Association and Traffic Between SGs and ASPs.....	93
5.2	ASP traffic Failover Examples.....	99
5.3	Normal Withdrawal of an ASP from an Application Server and Teardown of an Association.....	100
5.4	M3UA/MTP3-User Boundary Examples.....	101
5.5	Examples of IPSP communication.....	105
6.	Security Considerations.....	108
6.1	Introduction.....	108
6.2	Threats.....	108
6.3	Protecting Confidentiality.....	108
7.	IANA Considerations.....	109
7.1	SCTP Payload Protocol Identifier.....	109
7.2	M3UA Port Number.....	109
7.3	M3UA Protocol Extensions.....	109
8.	References.....	111
8.1	Normative References.....	111
8.2	Informative References.....	111
9.	Acknowledgements.....	113
10.	Document Contributors.....	113
	Appendix A.....	114
A.1	Signalling Network Architecture.....	114
A.2	Redundancy Models.....	117
	Editors' Addresses.....	119
	Full Copyright Statement.....	120

## 1. Introduction

This memo defines a protocol for supporting the transport of any SS7 MTP3-User signalling (e.g., ISUP and SCCP messages) over IP using the services of the Stream Control Transmission Protocol [17]. Also, provision is made for protocol elements that enable a seamless operation of the MTP3-User peers in the SS7 and IP domains. This protocol would be used between a Signalling Gateway (SG) and a Media Gateway Controller (MGC) or IP-resident Database [11], or between two IP-based applications.

### 1.1 Scope

There is a need for Switched Circuit Network (SCN) signalling protocol delivery from an SS7 Signalling Gateway (SG) to a Media Gateway Controller (MGC) or IP-resident Database as described in the Framework Architecture for Signalling Transport [11]. The delivery mechanism should meet the following criteria:

- \* Support for the transfer of all SS7 MTP3-User Part messages (e.g., ISUP [1,2,3], SCCP [4,5,6], TUP [12], etc.)
- \* Support for the seamless operation of MTP3-User protocol peers
- \* Support for the management of SCTP transport associations and traffic between an SG and one or more MGCs or IP-resident Databases
- \* Support for MGC or IP-resident Database process failover and load sharing
- \* Support for the asynchronous reporting of status changes to management

In simplistic transport terms, the SG will terminate SS7 MTP2 and MTP3 protocol layers [7,8,9] and deliver ISUP, SCCP and/or any other MTP3-User protocol messages, as well as certain MTP network management events, over SCTP transport associations to MTP3-User peers in MGCs or IP-resident Databases.

## 1.2 Terminology

Application Server (AS) - A logical entity serving a specific Routing Key. An example of an Application Server is a virtual switch element handling all call processing for a unique range of PSTN trunks, identified by an SS7 SIO/DPC/OPC/CIC\_range. Another example is a virtual database element, handling all HLR transactions for a particular SS7 DPC/OPC/SCCP\_SSN combination. The AS contains a set of one or more unique Application Server Processes, of which one or more is normally actively processing traffic. Note that there is a 1:1 relationship between an AS and a Routing Key.

Application Server Process (ASP) - A process instance of an Application Server. An Application Server Process serves as an active or backup process of an Application Server (e.g., part of a distributed virtual switch or database). Examples of ASPs are processes (or process instances) of MGCs, IP SCPs or IP HLRs. An ASP contains an SCTP endpoint and may be configured to process signalling traffic within more than one Application Server.

Association - An association refers to an SCTP association. The association provides the transport for the delivery of MTP3-User protocol data units and M3UA adaptation layer peer messages.

IP Server Process (IPSP) - A process instance of an IP-based application. An IPSP is essentially the same as an ASP, except that it uses M3UA in a point-to-point fashion. Conceptually, an IPSP does not use the services of a Signalling Gateway node.

Failover - The capability to reroute signalling traffic as required to an alternate Application Server Process, or group of ASPs, within an Application Server in the event of failure or unavailability of a currently used Application Server Process. Failover also applies upon the return to service of a previously unavailable Application Server Process.

Host - The computing platform that the process (SGP, ASP or IPSP) is running on.

Layer Management - Layer Management is a nodal function that handles the inputs and outputs between the M3UA layer and a local management entity.

Linkset - A number of signalling links that directly interconnect two signalling points, which are used as a module.

MTP - The Message Transfer Part of the SS7 protocol.

MTP3 - MTP Level 3, the signalling network layer of SS7

MTP3-User - Any protocol normally using the services of the SS7 MTP3 (e.g., ISUP, SCCP, TUP, etc.).

Network Appearance - The Network Appearance is a M3UA local reference shared by SG and AS (typically an integer) that together with an Signaling Point Code uniquely identifies an SS7 node by indicating the specific SS7 network it belongs to. It can be used to distinguish between signalling traffic associated with different networks being sent between the SG and the ASP over a common SCTP association. An example scenario is where an SG appears as an element in multiple separate national SS7 networks and the same Signaling Point Code value may be reused in different networks.

Network Byte Order: Most significant byte first, a.k.a Big Endian.

Routing Key: A Routing Key describes a set of SS7 parameters and parameter values that uniquely define the range of signalling traffic to be handled by a particular Application Server. Parameters within the Routing Key cannot extend across more than a single Signalling Point Management Cluster.

Routing Context - A value that uniquely identifies a Routing Key. Routing Context values are either configured using a configuration management interface, or by using the routing key management procedures defined in this document.

Signalling Gateway Process (SGP) - A process instance of a Signalling Gateway. It serves as an active, backup, load-sharing or broadcast process of a Signalling Gateway.

Signalling Gateway - An SG is a signaling agent that receives/sends SCN native signaling at the edge of the IP network [11]. An SG appears to the SS7 network as an SS7 Signalling Point. An SG contains a set of one or more unique Signalling Gateway Processes, of which one or more is normally actively processing traffic. Where an SG contains more than one SGP, the SG is a logical entity and the contained SGPs are assumed to be coordinated into a single management view to the SS7 network and to the supported Application Servers.

Signalling Process - A process instance that uses M3UA to communicate with other signalling processes. An ASP, an SGP and an IPSP are all signalling processes.

Signalling Point Management Cluster (SPMC) - The complete set of Application Servers represented to the SS7 network under a single MTP entity (Signalling Point) in one specific Network Appearance. SPMCs are used to aggregate the availability, congestion, and user part status of an MTP entity (Signalling Point) that is distributed in the IP domain, for the purpose of supporting MTP3 management procedures towards the SS7 network. In some cases, the SG itself may also be a member of the SPMC. In this case, the SG availability /congestion /User\_Part status should also be taken into account when considering any supporting MTP3 management actions.

Stream - A stream refers to an SCTP stream; a unidirectional logical channel established from one SCTP endpoint to another associated SCTP endpoint, within which all user messages are delivered in-sequence except for those submitted to the unordered delivery service.

### 1.3 M3UA Overview

#### 1.3.1 Protocol Architecture

The framework architecture that has been defined for SCN signalling transport over IP [11] uses multiple components, including a common signalling transport protocol and an adaptation module to support the services expected by a particular SCN signalling protocol from its underlying protocol layer.

Within the framework architecture, this document defines an MTP3-User adaptation module suitable for supporting the transfer of messages of any protocol layer that is identified to the MTP Level 3 as an MTP User. The list of these protocol layers includes, but is not limited to, ISDN User Part (ISUP) [1,2,3], Signalling Connection Control Part (SCCP) [4,5,6] and Telephone User Part (TUP) [12]. TCAP [13,14,15] or RANAP [16] messages are transferred transparently by the M3UA protocol as SCCP payload, as they are SCCP-User protocols.

It is recommended that M3UA use the services of the Stream Control Transmission Protocol (SCTP) [17] as the underlying reliable common signalling transport protocol. This is to take advantage of various SCTP features such as:

- Explicit packet-oriented delivery (not stream-oriented),
- Sequenced delivery of user messages within multiple streams, with an option for order-of-arrival delivery of individual user messages,
- Optional multiplexing of user messages into SCTP datagrams,
- Network-level fault tolerance through support of multi-homing at either or both ends of an association,
- Resistance to flooding and masquerade attacks, and
- Data segmentation to conform to discovered path MTU size.

Under certain scenarios, such as back-to-back connections without redundancy requirements, the SCTP functions above might not be a requirement and TCP MAY be used as the underlying common transport protocol.

### 1.3.2 Services Provided by the M3UA Layer

The M3UA Layer at an ASP or IPSP provides the equivalent set of primitives at its upper layer to the MTP3-Users as provided by the MTP Level 3 to its local MTP3-Users at an SS7 SEP. In this way, the ISUP and/or SCCP layer at an ASP or IPSP is unaware that the expected MTP3 services are offered remotely from an MTP3 Layer at an SGP, and not by a local MTP3 layer. The MTP3 layer at an SGP may also be unaware that its local users are actually remote user parts over M3UA. In effect, the M3UA extends access to the MTP3 layer services to a remote IP-based application. The M3UA layer does not itself provide the MTP3 services. However, in the case where an ASP is connected to more than one SG, the M3UA layer at an ASP should maintain the status of configured SS7 destinations and route messages according to the availability and congestion status of the routes to these destinations via each SG.

The M3UA layer may also be used for point-to-point signalling between two IP Server Processes (IPSPs). In this case, the M3UA layer provides the same set of primitives and services at its upper layer as the MTP3. However, in this case the expected MTP3 services are not offered remotely from an SGP. The MTP3 services are provided but the procedures to support these services are a subset of the MTP3 procedures due to the simplified point-to-point nature of the IPSP to IPSP relationship.

### 1.3.2.1 Support for the Transport of MTP3-User Messages

The M3UA layer provides the transport of MTP-TRANSFER primitives across an established SCTP association between an SGP and an ASP or between IPSPs.

At an ASP, in the case where a destination is reachable via multiple SGPs, the M3UA layer must also choose via which SGP the message is to be routed or support load balancing across the SGPs, minimizing missequencing.

The M3UA layer does not impose a 272-octet signalling information field (SIF) length limit as specified by the SS7 MTP Level 2 protocol [7,8,9]. Larger information blocks can be accommodated directly by M3UA/SCTP, without the need for an upper layer segmentation/re-assembly procedure as specified in recent SCCP or ISUP versions. However, in the context of an SG, the maximum 272-octet block size must be followed when interworking to a SS7 network that does not support the transfer of larger information blocks to the final destination. This avoids potential ISUP or SCCP fragmentation requirements at the SGPs. The provisioning and configuration of the SS7 network determines the restriction placed on the maximum block size. Some configurations (e.g., Broadband MTP [21]) may permit larger block sizes.

### 1.3.2.2 Native Management Functions

The M3UA layer provides the capability to indicate errors associated with received M3UA messages and to notify, as appropriate, local management and/or the peer M3UA.

### 1.3.2.3 Interworking with MTP3 Network Management Functions

At the SGP, the M3UA layer provides interworking with MTP3 management functions to support seamless operation of the user SCN signalling applications in the SS7 and IP domains. This includes:

- Providing an indication to MTP3-Users at an ASP that a destination in the SS7 network is not reachable.
- Providing an indication to MTP3-Users at an ASP that a destination in the SS7 network is now reachable.
- Providing an indication to MTP3-Users at an ASP that messages to a destination in the SS7 network are experiencing SS7 congestion.



- Providing an indication to the M3UA layer at an ASP that the routes to a destination in the SS7 network are restricted.
- Providing an indication to MTP3-Users at an ASP that a MTP3-User peer is unavailable.

The M3UA layer at an ASP keeps the state of the routes to remote SS7 destinations and may initiate an audit of the availability, the restricted or the congested state of remote SS7 destinations. This information is requested from the M3UA layer at the SGP.

The M3UA layer at an ASP may also indicate to the SG that the M3UA layer itself or the ASP or the ASP's Host is congested.

#### 1.3.2.4 Support for the Management of SCTP Associations between the SGP and ASPs.

The M3UA layer at the SGP maintains the availability state of all configured remote ASPs, to manage the SCTP Associations and the traffic between the M3UA peers. As well, the active/inactive and congestion state of remote ASPs is maintained.

The M3UA layer MAY be instructed by local management to establish an SCTP association to a peer M3UA node. This can be achieved using the M-SCTP\_ESTABLISH primitives (See Section 1.6.3 for a description of management primitives.) to request, indicate and confirm the establishment of an SCTP association with a peer M3UA node. In order to avoid redundant SCTP associations between two M3UA peers, one side (client) SHOULD be designated to establish the SCTP association, or M3UA configuration information maintained to detect redundant associations (e.g., via knowledge of the expected local and remote SCTP endpoint addresses).

Local management MAY request from the M3UA layer the status of the underlying SCTP associations using the M-SCTP\_STATUS request and confirm primitives. Also, the M3UA MAY autonomously inform local management of the reason for the release of an SCTP association, determined either locally within the M3UA layer or by a primitive from the SCTP.

Also the M3UA layer MAY inform the local management of the change in status of an ASP or AS. This MAY be achieved using the M-ASP\_STATUS request or M-AS\_STATUS request primitives.

### 1.3.2.5 Support for the Management of Connections to Multiple SGPs

As shown in Figure 1 an ASP may be connected to multiple SGPs. In such a case a particular SS7 destination may be reachable via more than one SGP and/or SG, i.e., via more than one route. As MTP3 users only maintain status on a destination and not on a route basis, the M3UA layer must maintain the status (availability, restriction, and/or congestion of route to destination) of the individual routes, derive the overall availability or congestion status of the destination from the status of the individual routes, and inform the MTP3 users of this derived status whenever it changes.

## 1.4 Functional Areas

### 1.4.1 Signalling Point Code Representation

For example, within an SS7 network, a Signalling Gateway might be charged with representing a set of nodes in the IP domain into the SS7 network for routing purposes. The SG itself, as a signalling point in the SS7 network, might also be addressable with an SS7 Point Code for MTP3 Management purposes. The SG Point Code might also be used for addressing any local MTP3-Users at the SG such as a local SCCP layer.

An SG may be logically partitioned to operate in multiple SS7 network appearances. In such a case, the SG could be addressable with a Point Code in each network appearance, and represents a set of nodes in the IP domain into each SS7 network. Alias Point Codes [8] may also be used within an SG network appearance.

Where an SG contains more than one SGP, the MTP3 routeset, SPMC and remote AS/ASP states of each SGP SHOULD be coordinated across all the SGPs. Rerouting of traffic between the SGPs MAY also be supported.

Application Servers can be represented under the same Point Code of the SG, their own individual Point Codes or grouped with other Application Servers for Point Code preservation purposes. A single Point Code may be used to represent the SG and all the Application Servers together, if desired.

If an ASP or group of ASPs is available to the SS7 network via more than one SG, each with its own Point Code, the ASP(s) will typically be represented by a Point Code that is separate from any SG Point Code. This allows, for example, these SGs to be viewed from the SS7 network as "STPs", each having an ongoing "route" to the same ASP(s). Under failure conditions where the ASP(s) become(s) unavailable from one of the SGs, this approach enables MTP3 route management messaging between the SG and SS7 network, allowing simple SS7 rerouting through

an alternate SG without changing the Destination Point Code Address of SS7 traffic to the ASP(s).

Where a particular AS can be reached via more than one SGP, the corresponding Routing Keys in the SGPs should be identical. (Note: It is possible for the SGP Routing Key configuration data to be temporarily out-of-sync during configuration updates).




Figure 1 Example with mated SGs

\* Note: SG-to-SG communication (i.e., "C-links") is recommended for carrier grade networks, using an MTP3 linkset or an equivalent, to allow rerouting between the SGs in the event of route failures. Where SGPs are used, inter-SGP communication might be used. Inter-SGP protocol is outside of the scope of this document.

The following example shows a signalling gateway partitioned into two network appearances.




Figure 2 Example with multiple Network

## 1.4.2 Routing Contexts and Routing Keys

### 1.4.2.1 Overview

The distribution of SS7 messages between the SGP and the Application Servers is determined by the Routing Keys and their associated Routing Contexts. A Routing Key is essentially a set of SS7 parameters used to filter SS7 messages, whereas the Routing Context parameter is a 4-byte value (integer) that is associated to that Routing Key in a 1:1 relationship. The Routing Context therefore can be viewed as an index into a sending node's Message Distribution Table containing the Routing Key entries.

Possible SS7 address/routing information that comprise a Routing Key entry includes, for example, the OPC, DPC, SIO found in the MTP3 routing label, or MTP3-User specific fields (such as the ISUP CIC, SCCP subsystem number). Some example Routing Keys are: the DPC alone, the DPC/OPC combination, the DPC/OPC/CIC combination, or the DPC/SSN combination. The particular information used to define an M3UA Routing Key is application and network dependent, and none of the above examples are mandated.

An Application Server Process may be configured to process signalling traffic related to more than one Application Server, over a single SCTP Association. In ASP Active and ASP Inactive management messages, the signalling traffic to be started or stopped is discriminated by the Routing Context parameter. At an ASP, the Routing Context parameter uniquely identifies the range of signalling traffic associated with each Application Server that the ASP is configured to receive.

### 1.4.2.2 Routing Key Limitations

Routing Keys SHOULD be unique in the sense that each received SS7 signalling message SHOULD have a full or partial match to a single routing result. It is not necessary for the parameter range values within a particular Routing Key to be contiguous. For example, an AS could be configured to support call processing for multiple ranges of PSTN trunks that are not represented by contiguous CIC values.

### 1.4.2.3 Managing Routing Contexts and Routing Keys

There are two ways to provision a Routing Key at an SGP. A Routing Key may be configured statically using an implementation dependent management interface, or dynamically using the M3UA Routing Key registration procedure.

When using a management interface to configure Routing Keys, the message distribution function within the SGP is not limited to the set of parameters defined in this document. Other implementation dependent distribution algorithms may be used.

#### 1.4.2.4 Message Distribution at the SGP

To direct messages received from the SS7 MTP3 network to the appropriate IP destination, the SGP must perform a message distribution function using information from the received MTP3-User message.

To support this message distribution, the SGP might, for example, maintain the equivalent of a network address translation table, mapping incoming SS7 message information to an Application Server for a particular application and range of traffic. This could be accomplished by comparing elements of the incoming SS7 message to currently defined Routing Keys in the SGP.

These Routing Keys could in turn map directly to an Application Server that is enabled by one or more ASPs. These ASPs provide dynamic status information regarding their availability, traffic handling capability and congestion to the SGP using various management messages defined in the M3UA protocol.

The list of ASPs in an AS is assumed to be dynamic, taking into account the availability, traffic handling capability and congestion status of the individual ASPs in the list, as well as configuration changes and possible failover mechanisms.

Normally, one or more ASPs are active (i.e., currently processing traffic) in the AS but in certain failure and transition cases it is possible that there may be no active ASP available. Broadcast, loadsharing and backup scenarios are supported.

When there is no matching Routing Key entry for an incoming SS7 message, a default treatment MAY be specified. Possible solutions are to provide a default Application Server at the SGP that directs all unallocated traffic to a (set of) default ASP(s), or to drop the message and provide a notification to layer management. The treatment of unallocated traffic is implementation dependent.

#### 1.4.2.5 Message Distribution at the ASP

The ASP must choose an SGP to direct a message to the SS7 network. This is accomplished by observing the Destination Point Code (and possibly other elements of the outgoing message such as the SLS value). The ASP must also take into account whether the related Routing Context is active or not (See Section 4.3.4.3).

Implementation Note: Where more than one route (or SGP) is possible for routing to the SS7 network, the ASP could, for example, maintain a dynamic table of available SGP routes for the SS7 destinations, taking into account the SS7 destination availability/restricted/congestion status received from the SGP(s), the availability status of the individual SGPs and configuration changes and failover mechanisms. There is, however, no M3UA messaging to manage the status of an SGP (e.g., SGP-Up/Down/Active/Inactive messaging).

Whenever an SCTP association to an SGP exists, the SGP is assumed to be ready for the purposes of responding to M3UA ASPSM messages (Refer to Section 3).

#### 1.4.3 SS7 and M3UA Interworking

In the case of SS7 and M3UA interworking, the M3UA adaptation layer is designed to provide an extension of the MTP3 defined user primitives.

##### 1.4.3.1 Signalling Gateway SS7 Layers

The SG is responsible for terminating MTP Level 3 of the SS7 protocol, and offering an IP-based extension to its users.

From an SS7 perspective, it is expected that the Signalling Gateway transmits and receives SS7 Message Signalling Units (MSUs) to and from the PSTN over a standard SS7 network interface, using the SS7 Message Transfer Part (MTP) [7,8,9] to provide reliable transport of the messages.

As a standard SS7 network interface, the use of MTP Level 2 signalling links is not the only possibility. ATM-based High Speed Links can also be used with the services of the Signalling ATM Adaptation Layer (SAAL) [18,19].

Note: It is also possible for IP-based interfaces to be present, using the services of the MTP2-User Adaptation Layer (M2UA) [27] or M2PA [28].

These could be terminated at a Signalling Transfer Point (STP) or Signalling End Point (SEP). Using the services of MTP3, the SG could be capable of communicating with remote SS7 SEPs in a quasi-associated fashion, where STPs may be present in the SS7 path between the SEP and the SG.

#### 1.4.3.2 SS7 and M3UA Interworking at the SG

The SGP provides a functional interworking of transport functions between the SS7 network and the IP network by also supporting the M3UA adaptation layer. It allows the transfer of MTP3-User signalling messages to and from an IP-based Application Server Process where the peer MTP3-User protocol layer exists.

For SS7 user part management, it is required that the MTP3-User protocols at ASPs receive indications of SS7 signalling point availability, SS7 network congestion, and remote User Part unavailability as would be expected in an SS7 SEP node. To accomplish this, the MTP-PAUSE, MTP-RESUME and MTP-STATUS indication primitives received at the MTP3 upper layer interface at the SG need to be propagated to the remote MTP3-User lower layer interface at the ASP.

MTP3 management messages (such as TFPs or TFAs received from the SS7 network) MUST NOT be encapsulated as Data message Payload Data and sent either from SG to ASP or from ASP to SG. The SG MUST terminate these messages and generate M3UA messages as appropriate.

#### 1.4.3.3 Application Server

A cluster of application servers is responsible for providing the overall support for one or more SS7 upper layers. From an SS7 standpoint, a Signalling Point Management Cluster (SPMC) provides complete support for the upper layer service for a given point code. As an example, an SPMC providing MGC capabilities could provide complete support for ISUP (and any other MTP3 user located at the point code of the SPMC) for a given point code.

In the case where an ASP is connected to more than one SGP, the M3UA layer must maintain the status of configured SS7 destinations and route messages according to availability/congestion/restricted status of the routes to these SS7 destinations.

#### 1.4.3.4 IPSP Considerations

Since IPSPs use M3UA in a point-to-point fashion, there is no concept of routing of messages beyond the remote end. Therefore, SS7 and M3UA interworking is not necessary for this model.

#### 1.4.4 Redundancy Models

##### 1.4.4.1 Application Server Redundancy

All MTP3-User messages (e.g., ISUP, SCCP) which match a provisioned Routing Key at an SGP are mapped to an Application Server.

The Application Server is the set of all ASPs associated with a specific Routing Key. Each ASP in this set may be active, inactive or unavailable. Active ASPs handle traffic; inactive ASPs might be used when active ASPs become unavailable.

The failover model supports an "n+k" redundancy model, where "n" ASPs is the minimum number of redundant ASPs required to handle traffic and "k" ASPs are available to take over for a failed or unavailable ASP. A "1+1" active/backup redundancy is a subset of this model. A simplex "1+0" model is also supported as a subset, with no ASP redundancy.

##### 1.4.5 Flow Control

Local Management at an ASP may wish to stop traffic across an SCTP association to temporarily remove the association from service or to perform testing and maintenance activity. The function could optionally be used to control the start of traffic on to a newly available SCTP association.

##### 1.4.6 Congestion Management

The M3UA layer is informed of local and IP network congestion by means of an implementation-dependent function (e.g., an implementation dependent indication from the SCTP of IP network congestion).

At an ASP or IPSP, the M3UA layer indicates congestion to local MTP3-Users by means of an MTP-STATUS primitive, as per current MTP3 procedures, to invoke appropriate upper layer responses.

When an SG determines that the transport of SS7 messages to a Signalling Point Management Cluster (SPMC) is encountering congestion, the SG MAY trigger SS7 MTP3 Transfer Controlled management messages to originating SS7 nodes, per the congestion procedures of the relevant MTP3 standard. The triggering of SS7 MTP3 Management messages from an SG is an implementation-dependent function.



The M3UA layer at an ASP or IPSP MAY indicate local congestion to an M3UA peer with an SCON message. When an SG receives a congestion message (SCON) from an ASP, and the SG determines that an SPMC is now encountering congestion, it MAY trigger SS7 MTP3 Transfer Controlled management messages to concerned SS7 destinations according to congestion procedures of the relevant MTP3 standard.

#### 1.4.7 SCTP Stream Mapping.

The M3UA layer at both the SGP and ASP also supports the assignment of signalling traffic into streams within an SCTP association. Traffic that requires sequencing SHOULD be assigned to the same stream. To accomplish this, MTP3-User traffic may be assigned to individual streams based on, for example, the SLS value in the MTP3 Routing Label or the ISUP CIC assignment, subject of course to the maximum number of streams supported by the underlying SCTP association.

#### 1.4.8 Client/Server Model


It is recommended that the SGP and ASP be able to support both client and server operation. The peer endpoints using M3UA SHOULD be configured so that one always takes on the role of client and the other the role of server for initiating SCTP associations. The default orientation would be for the SGP to take on the role of server while the ASP is the client. In this case, ASPs SHOULD initiate the SCTP association to the SGP.

In the case of IPSP to IPSP communication, the peer endpoints using M3UA SHOULD be configured so that one always takes on the role of client and the other the role of server for initiating SCTP associations.

The SCTP and TCP Registered User Port Number Assignment for M3UA is 2905.

## 1.5 Sample Configuration

### 1.5.1 Example 1: ISUP Message Transport



SEP - SS7 Signalling End Point


SCTP - Stream Control Transmission Protocol

NIF - Nodal Interworking Function

In this example, the SGP provides an implementation-dependent nodal interworking function (NIF) that allows the MGC to exchange SS7 signalling messages with the SS7-based SEP. The NIF within the SGP serves as the interface within the SGP between the MTP3 and M3UA. This nodal interworking function has no visible peer protocol with either the MGC or SEP. It also provides network status information to one or both sides of the network.


For internal SGP modeling purposes, at the NIF level, SS7 signalling messages that are destined to the MGC are received as MTP-TRANSFER indication primitives from the MTP Level 3 upper layer interface, translated to MTP-TRANSFER request primitives, and sent to the local M3UA-resident message distribution function for ongoing routing to the final IP destination. Messages received from the local M3UA network address translation and mapping function as MTP-TRANSFER indication primitives are sent to the MTP Level 3 upper layer interface as MTP-TRANSFER request primitives for ongoing MTP Level 3 routing to an SS7 SEP. For the purposes of providing SS7 network status information the NIF also delivers MTP-PAUSE, MTP-RESUME and MTP-STATUS indication primitives received from the MTP Level 3 upper layer interface to the local M3UA-resident management function. In addition, as an implementation and network option, restricted destinations are communicated from MTP network management to the local M3UA-resident management function.

## 1.5.2 Example 2: SCCP Transport between IPSPs



This example shows an architecture where no Signalling Gateway is used. In this example, SCCP messages are exchanged directly between two IP-resident IPSPs with resident SCCP-User protocol instances, such as RANAP or TCAP. SS7 network interworking is not required, therefore there is no MTP3 network management status information for the SCCP and SCCP-User protocols to consider. Any MTP-PAUSE, MTP-RESUME or MTP-STATUS indications from the M3UA layer to the SCCP layer should consider the status of the Sctp Association and underlying IP network and any congestion information received from the remote site.

## 1.5.3 Example 3: SGP Resident SCCP Layer, with Remote ASP



STP - SS7 Signalling Transfer Point

In this example, the SGP contains an instance of the SS7 SCCP protocol layer that may, for example, perform the SCCP Global Title Translation (GTT) function for messages logically addressed to the SG SCCP. If the result of a GTT for an SCCP message yields an SS7 DPC or DPC/SSN address of an SCCP peer located in the IP domain, the resulting MTP-TRANSFER request primitive is sent to the local M3UA-resident network address translation and mapping function for ongoing routing to the final IP destination.

Similarly, the SCCP instance in an SGP can perform the SCCP GTT service for messages logically addressed to it from SCCP peers in the IP domain. In this case, MTP-TRANSFER indication primitives are sent from the local M3UA-resident network address translation and mapping function to the SCCP for GTT. If the result of the GTT yields the address of an SCCP peer in the SS7 network then the resulting MTP-TRANSFER request primitive is given to the MTP3 for delivery to an SS7-resident node.

It is possible that the above SCCP GTT at the SGP could yield the address of an SCCP peer in the IP domain and the resulting MTP-TRANSFER request primitive would be sent back to the M3UA layer for delivery to an IP destination.

For internal SGP modeling purposes, this may be accomplished with the use of an implementation-dependent nodal interworking function within the SGP that effectively sits below the SCCP and routes MTP-TRANSFER request/indication messages to/from both the MTP3 and the M3UA layer, based on the SS7 DPC or DPC/SSN address information. This nodal interworking function has no visible peer protocol with either the ASP or SEP.

Note that the services and interface provided by the M3UA layer are the same as in Example 1 and the functions taking place in the SCCP entity are transparent to the M3UA layer. The SCCP protocol functions are not reproduced in the M3UA protocol.

## 1.6 Definition of M3UA Boundaries

### 1.6.1 Definition of the Boundary between M3UA and an MTP3-User.

From ITU Q.701 [7]:

- MTP-TRANSFER request
- MTP-TRANSFER indication
- MTP-PAUSE indication
- MTP-RESUME indication
- MTP-STATUS indication

### 1.6.2 Definition of the Boundary between M3UA and SCTP

An example of the upper layer primitives provided by the SCTP are provided in Reference [17] Section 10.

### 1.6.3 Definition of the Boundary between M3UA and Layer Management

M-SCTP\_ESTABLISH request  
Direction: LM -> M3UA  
Purpose: LM requests ASP to establish an SCTP association with its peer.

M-STCP\_ESTABLISH confirm  
Direction: M3UA -> LM  
Purpose: ASP confirms to LM that it has established an SCTP association with its peer.

M-SCTP\_ESTABLISH indication  
Direction: M3UA -> LM  
Purpose: M3UA informs LM that a remote ASP has established an SCTP association.

M-SCTP\_RELEASE request

Direction: LM -> M3UA

Purpose: LM requests ASP to release an SCTP association with its peer.

M-SCTP\_RELEASE confirm

Direction: M3UA -> LM

Purpose: ASP confirms to LM that it has released SCTP association with its peer.

M-SCTP\_RELEASE indication

Direction: M3UA -> LM

Purpose: M3UA informs LM that a remote ASP has released an SCTP Association or the SCTP association has failed.

M-SCTP\_RESTART indication

Direction: M3UA -> LM

Purpose: M3UA informs LM that an SCTP restart indication has been received.

M-SCTP\_STATUS request

Direction: LM -> M3UA

Purpose: LM requests M3UA to report the status of an SCTP association.

M-SCTP\_STATUS confirm

Direction: M3UA -> LM

Purpose: M3UA responds with the status of an SCTP association.

M-SCTP STATUS indication

Direction: M3UA -> LM

Purpose: M3UA reports the status of an SCTP association.

M-ASP\_STATUS request

Direction: LM -> M3UA

Purpose: LM requests M3UA to report the status of a local or remote ASP.

M-ASP\_STATUS confirm

Direction: M3UA -> LM

Purpose: M3UA reports status of local or remote ASP.

M-AS\_STATUS request

Direction: LM -> M3UA

Purpose: LM requests M3UA to report the status of an AS.

M-AS\_STATUS confirm

Direction: M3UA -> LM

Purpose: M3UA reports the status of an AS.

M-NOTIFY indication

Direction: M3UA -> LM

Purpose: M3UA reports that it has received a Notify message from its peer.

M-ERROR indication

Direction: M3UA -> LM

Purpose: M3UA reports that it has received an Error message from its peer or that a local operation has been unsuccessful.

M-ASP\_UP request

Direction: LM -> M3UA

Purpose: LM requests ASP to start its operation and send an ASP Up message to its peer.

M-ASP\_UP confirm

Direction: M3UA -> LM

Purpose: ASP reports that it has received an ASP UP Ack message from its peer.

M-ASP\_UP indication

Direction: M3UA -> LM

Purpose: M3UA reports it has successfully processed an incoming ASP Up message from its peer.

M-ASP\_DOWN request

Direction: LM -> M3UA

Purpose: LM requests ASP to stop its operation and send an ASP Down message to its peer.

M-ASP\_DOWN confirm

Direction: M3UA -> LM

Purpose: ASP reports that it has received an ASP Down Ack message from its peer.

M-ASP\_DOWN indication

Direction: M3UA -> LM

Purpose: M3UA reports it has successfully processed an incoming ASP Down message from its peer, or the SCTP association has been lost/reset.

M-ASP\_ACTIVE request

Direction: LM -> M3UA

Purpose: LM requests ASP to send an ASP Active message to its peer.

M-ASP\_ACTIVE confirm

Direction: M3UA -> LM

Purpose: ASP reports that it has received an ASP Active  
Ack message from its peer.

M-ASP\_ACTIVE indication

Direction: M3UA -> LM

Purpose: M3UA reports it has successfully processed an incoming ASP  
Active message from its peer.

M-ASP\_INACTIVE request

Direction: LM -> M3UA

Purpose: LM requests ASP to send an ASP Inactive message to its  
peer.

M-ASP\_INACTIVE confirm

Direction: LM -> M3UA

Purpose: ASP reports that it has received an ASP Inactive  
Ack message from its peer.

M-ASP\_INACTIVE indication

Direction: M3UA -> LM

Purpose: M3UA reports it has successfully processed an incoming ASP  
Inactive message from its peer.

M-AS\_ACTIVE indication

Direction: M3UA -> LM

Purpose: M3UA reports that an AS has moved to the AS-ACTIVE state.

M-AS\_INACTIVE indication

Direction: M3UA -> LM

Purpose: M3UA reports that an AS has moved to the AS-INACTIVE state.

M-AS\_DOWN indication

Direction: M3UA -> LM

Purpose: M3UA reports that an AS has moved to the AS-DOWN state.

If dynamic registration of RK is supported by the M3UA layer, the  
layer MAY support the following additional primitives:

M-RK\_REG request

Direction: LM -> M3UA

Purpose: LM requests ASP to register RK(s) with its peer by sending  
REG REQ message



M-RK\_REG confirm

Direction: M3UA -> LM

Purpose: ASP reports that it has received REG RSP message with registration status as successful from its peer.

M-RK\_REG indication

Direction: M3UA -> LM

Purpose: M3UA informs LM that it has successfully processed an incoming REG REQ message.

M-RK\_DEREG request

Direction: LM -> M3UA

Purpose: LM requests ASP to deregister RK(s) with its peer by sending DEREG REQ message.

M-RK\_DEREG confirm

Direction: M3UA -> LM

Purpose: ASP reports that it has received DEREG REQ message with deregistration status as successful from its peer.

M-RK\_DEREG indication

Direction: M3UA -> LM

Purpose: M3UA informs LM that it has successfully processed an incoming DEREG REQ from its peer.

## 2. Conventions


The keywords MUST, MUST NOT, REQUIRED, SHALL, SHALL NOT, SHOULD, SHOULD NOT, RECOMMENDED, NOT RECOMMENDED, MAY, and OPTIONAL, when they appear in this document, are to be interpreted as described in [20].

## 3. M3UA Protocol Elements

The general M3UA message format includes a Common Message Header followed by zero or more parameters as defined by the Message Type. For forward compatibility, all Message Types may have attached parameters even if none are specified in this version.

### 3.1 Common Message Header

The protocol messages for MTP3-User Adaptation require a message header which contains the adaptation layer version, the message type, and message length.



All fields in an M3UA message MUST be transmitted in the network byte order, unless otherwise stated.

#### 3.1.1 M3UA Protocol Version: 8 bits (unsigned integer)

The version field contains the version of the M3UA adaptation layer.

The supported versions are the following:

1 Release 1.0

#### 3.1.2 Message Classes and Types

The following list contains the valid Message Classes:

Message Class: 8 bits (unsigned integer)

The following list contains the valid Message Type Classes:

- 0 Management (MGMT) Messages
- 1 Transfer Messages
- 2 SS7 Signalling Network Management (SSNM) Messages
- 3 ASP State Maintenance (ASPSM) Messages
- 4 ASP Traffic Maintenance (ASPTM) Messages
- 5 Reserved for Other Sigtran Adaptation Layers
- 6 Reserved for Other Sigtran Adaptation Layers
- 7 Reserved for Other Sigtran Adaptation Layers
- 8 Reserved for Other Sigtran Adaptation Layers
- 9 Routing Key Management (RKM) Messages
- 10 to 127 Reserved by the IETF
- 128 to 255 Reserved for IETF-Defined Message Class extensions

Message Type: 8 bits (unsigned integer)

The following list contains the message types for the defined messages.

Management (MGMT) Messages (See Section 3.8)

0	Error (ERR)
1	Notify (NTFY)
2 to 127	Reserved by the IETF
128 to 255	Reserved for IETF-Defined MGMT extensions

Transfer Messages (See Section 3.3)

0	Reserved
1	Payload Data (DATA)
2 to 127	Reserved by the IETF
128 to 255	Reserved for IETF-Defined Transfer extensions

SS7 Signalling Network Management (SSNM) Messages (See Section 3.4)

0	Reserved
1	Destination Unavailable (DUNA)
2	Destination Available (DAVA)
3	Destination State Audit (DAUD)
4	Signalling Congestion (SCON)
5	Destination User Part Unavailable (DUPU)
6	Destination Restricted (DRST)
7 to 127	Reserved by the IETF
128 to 255	Reserved for IETF-Defined SSNM extensions

ASP State Maintenance (ASPSM) Messages (See Section 3.5)

0	Reserved
1	ASP Up (ASPUP)
2	ASP Down (ASPDN)
3	Heartbeat (BEAT)
4	ASP Up Acknowledgement (ASPUP ACK)
5	ASP Down Acknowledgement (ASPDN ACK)
6	Heartbeat Acknowledgement (BEAT ACK)
7 to 127	Reserved by the IETF
128 to 255	Reserved for IETF-Defined ASPSM extensions

## ASP Traffic Maintenance (ASPTM) Messages (See Section 3.7)

0	Reserved
1	ASP Active (ASPAC)
2	ASP Inactive (ASPIA)
3	ASP Active Acknowledgement (ASPAC ACK)
4	ASP Inactive Acknowledgement (ASPIA ACK)
5 to 127	Reserved by the IETF
128 to 255	Reserved for IETF-Defined ASPTM extensions

## Routing Key Management (RKM) Messages (See Section 3.6)

0	Reserved
1	Registration Request (REG REQ)
2	Registration Response (REG RSP)
3	Deregistration Request (DEREG REQ)
4	Deregistration Response (DEREG RSP)
5 to 127	Reserved by the IETF
128 to 255	Reserved for IETF-Defined RKM extensions

## 3.1.3 Reserved: 8 bits

The Reserved field SHOULD be set to all '0's and ignored by the receiver.


## 3.1.4 Message Length: 32-bits (unsigned integer)

The Message Length defines the length of the message in octets, including the Common Header. The Message Length MUST include parameter padding bytes, if any.

Note: A receiver SHOULD accept the message whether or not the final parameter padding is included in the message length.

### 3.2 Variable Length Parameter Format

M3UA messages consist of a Common Header followed by zero or more variable length parameters, as defined by the message type. All the parameters contained in a message are defined in a Tag Length-Value format as shown below.



Where more than one parameter is included in a message, the parameters may be in any order, except where explicitly mandated. A receiver SHOULD accept the parameters in any order.

Parameter Tag: 16 bits (unsigned integer)

The Tag field is a 16-bit identifier of the type of parameter. It takes a value of 0 to 65534. Common parameters used by adaptation layers are in the range of 0x00 to 0x3f. M3UA-specific parameters have Tags in the range 0x0200 to 0x02ff. The parameter Tags defined are as follows:

Common Parameters. These TLV parameters are common across the different adaptation layers:

Parameter Name =====	Parameter ID =====
Reserved	0x0000
Not Used in M3UA	0x0001
Not Used in M3UA	0x0002
Not Used in M3UA	0x0003
INFO String	0x0004
Not Used in M3UA	0x0005
Routing Context	0x0006
Diagnostic Information	0x0007
Not Used in M3UA	0x0008
Heartbeat Data	0x0009
Not Used in M3UA	0x000a
Traffic Mode Type	0x000b
Error Code	0x000c
Status	0x000d

Not Used in M3UA	0x000e
Not Used in M3UA	0x000f
Not Used in M3UA	0x0010
ASP Identifier	0x0011
Affected Point Code	0x0012
Correlation ID	0x0013

M3UA-Specific parameters. These TLV parameters are specific to the M3UA protocol:

Network Appearance	0x0200
Reserved	0x0201
Reserved	0x0202
Reserved	0x0203
User/Cause	0x0204
Congestion Indications	0x0205
Concerned Destination	0x0206
Routing Key	0x0207
Registration Result	0x0208
Deregistration Result	0x0209
Local_Routing Key Identifier	0x020a
Destination Point Code	0x020b
Service Indicators	0x020c
Reserved	0x020d
Originating Point Code List	0x020e
Circuit Range	0x020f
Protocol Data	0x0210
Reserved	0x0211
Registration Status	0x0212
Deregistration Status	0x0213
Reserved by the IETF	0x0214 to 0xffff

The value of 65535 is reserved for IETF-defined extensions. Values other than those defined in specific parameter description are reserved for use by the IETF.

Parameter Length: 16 bits (unsigned integer)

The Parameter Length field contains the size of the parameter in bytes, including the Parameter Tag, Parameter Length, and Parameter Value fields. Thus, a parameter with a zero-length Parameter Value field would have a Length field of 4. The Parameter Length does not include any padding bytes.

Parameter Value: variable length.

The Parameter Value field contains the actual information to be transferred in the parameter.

The total length of a parameter (including Tag, Parameter Length and Value fields) MUST be a multiple of 4 bytes. If the length of the parameter is not a multiple of 4 bytes, the sender pads the Parameter at the end (i.e., after the Parameter Value field) with all zero bytes. The length of the padding is NOT included in the parameter length field. A sender SHOULD NOT pad with more than 3 bytes. The receiver MUST ignore the padding bytes.

### 3.3 Transfer Messages


The following section describes the Transfer messages and parameter contents.

#### 3.3.1 Payload Data Message (DATA)

The DATA message contains the SS7 MTP3-User protocol data, which is an MTP-TRANSFER primitive, including the complete MTP3 Routing Label. The DATA message contains the following variable length parameters:

Network Appearance	Optional
Routing Context	Optional
Protocol Data	Mandatory
Correlation Id	Optional

The following format MUST be used for the Data Message:



Network Appearance: 32-bits (unsigned integer)

The Network Appearance parameter identifies the SS7 network context for the message and implicitly identifies the SS7 Point Code format used, the SS7 Network Indicator value, and the MTP3 and possibly the MTP3-User protocol type/variant/version used within the specific SS7 network. Where an SG operates in the context of a single SS7 network, or individual SCTP associations are dedicated to each SS7 network context, the Network Appearance parameter is not required. In other cases the parameter may be configured to be present for the use of the receiver.

The Network Appearance parameter value is of local significance only, coordinated between the SGP and ASP. Therefore, in the case where an ASP is connected to more than one SGP, the same SS7 network context may be identified by different Network Appearance values depending over which SGP a message is being transmitted/received.

Where the optional Network Appearance parameter is present, it must be the first parameter in the message as it defines the format of the Protocol Data field.



IMPLEMENTATION NOTE: For simplicity of configuration it may be desirable to use the same NA value across all nodes sharing a particular network context.

Routing Context: 32-bits (unsigned integer)

The Routing Context parameter contains the Routing Context value associated with the DATA message. Where a Routing Key has not been coordinated between the SGP and ASP, sending of Routing Context is not required. Where multiple Routing Keys and Routing Contexts are used across a common association, the Routing Context MUST be sent to identify the traffic flow, assisting in the internal distribution of Data messages.

Protocol Data: variable length

The Protocol Data parameter contains the original SS7 MTP3 message, including the Service Information Octet and Routing Label.

The Protocol Data parameter contains the following fields:

- Service Indicator,
- Network Indicator,
- Message Priority.


- Destination Point Code,
- Originating Point Code,

- Signalling Link Selection Code (SLS).

User Protocol Data. Includes:

- MTP3-User protocol elements (e.g., ISUP, SCCP, or TUP parameters).

The Protocol Data parameter is encoded as follows:



Originating Point Code: 32 bits (unsigned integer)

Destination Point Code: 32 bits (unsigned integer)

The Originating and Destination Point Code fields contains the OPC and DPC from the routing label of the original SS7 message in Network Byte Order, justified to the least significant bit. Unused bits are coded '0'.

Service Indicator: 8 bits (unsigned integer)

The Service Indicator field contains the SI field from the original SS7 message justified to the least significant bit. Unused bits are coded '0'.

Network Indicator: 8-bits (unsigned integer)

The Network Indicator contains the NI field from the original SS7 message justified to the least significant bit. Unused bits are coded '0'.

Message Priority: 8 bits (unsigned integer)

The Message Priority field contains the MP bits (if any) from the original SS7 message, both for ANSI-style and TTC-style [29] message priority bits. The MP bits are aligned to the least significant bit. Unused bits are coded '0'.

Signalling Link Selection: 8 bits (unsigned integer)

The Signalling Link Selection field contains the SLS bits from the routing label of the original SS7 message justified to the least significant bit and in Network Byte Order. Unused bits are coded '0'.

User Protocol Data: (byte string)

The User Protocol Data field contains a byte string of MTP-User information from the original SS7 message starting with the first byte of the original SS7 message following the Routing Label.

Correlation Id: 32-bits (unsigned integer)

The Correlation Id parameter uniquely identifies the MSU carried in the Protocol Data within an AS. This Correlation Id parameter is assigned by the sending M3UA.

### 3.4 SS7 Signalling Network Management (SSNM) Messages

#### 3.4.1 Destination Unavailable (DUNA)

The DUNA message is sent from an SGP in an SG to all concerned ASPs to indicate that the SG has determined that one or more SS7 destinations are unreachable. It is also sent by an SGP in response to a message from the ASP to an unreachable SS7 destination. As an implementation option the SG may suppress the sending of subsequent "response" DUNA messages regarding a certain unreachable SS7 destination for a certain period to give the remote side time to react. If there is no alternate route via another SG, the MTP3-User at the ASP is expected to stop traffic to the affected destination via the SG as per the defined MTP3-User procedures.

The DUNA message contains the following parameters:

Network Appearance	Optional
Routing Context	Optional
Affected Point Code	Mandatory
INFO String	Optional

The format for DUNA Message parameters is as follows:

```

      0               1               2               3
      0 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1
+-----+-----+-----+-----+-----+-----+-----+-----+
|               Tag = 0x0200               |               Length = 8               |
+-----+-----+-----+-----+-----+-----+-----+-----+
|               Network Appearance               |
+-----+-----+-----+-----+-----+-----+-----+-----+
|               Tag = 0x0006               |               Length               |
+-----+-----+-----+-----+-----+-----+-----+-----+
\
/               Routing Context               /
\
+-----+-----+-----+-----+-----+-----+-----+-----+
|               Tag = 0x0012               |               Length               |
+-----+-----+-----+-----+-----+-----+-----+-----+
|               Mask               |               Affected PC 1               |
+-----+-----+-----+-----+-----+-----+-----+-----+
\
/               ...               /
\
+-----+-----+-----+-----+-----+-----+-----+-----+
|               Mask               |               Affected PC n               |
+-----+-----+-----+-----+-----+-----+-----+-----+
|               Tag = 0x0004               |               Length               |
+-----+-----+-----+-----+-----+-----+-----+-----+
\
/               INFO String               /
\
+-----+-----+-----+-----+-----+-----+-----+-----+

```

Network Appearance: 32-bit unsigned integer


See Section 3.3.1

Routing Context: n x 32-bits (unsigned integer)

The optional Routing Context parameter contains the Routing Context values associated with the DUNA message. Where a Routing Key has not been coordinated between the SGP and ASP, sending of

Affected Point Code: n x 32-bits

ANSI 24-bit Point Code:

[illegible]

[Page 37]

Mask: 8-bits (unsigned integer)

The Mask field can be used to identify a contiguous range of Affected Destination Point Codes. Identifying a contiguous range of Affected DPCs may be useful when reception of an MTP3 management message or a linkset event simultaneously affects the availability status of a series of destinations at an SG.

The Mask parameter is an integer representing a bit mask that can be applied to the related Affected PC field. The bit mask identifies how many bits of the Affected PC field are significant and which are effectively "wildcarded". For example, a mask of "8" indicates that the last eight bits of the PC is "wildcarded". For an ANSI 24-bit Affected PC, this is equivalent to signalling that all PCs in an ANSI Cluster are unavailable. A mask of "3" indicates that the last three bits of the PC is "wildcarded". For a 14-bit ITU Affected PC, this is equivalent to signaling that an ITU

Region is unavailable. A mask value equal (or greater than) the number of bits in the PC indicates that the entire network appearance is affected - this is used to indicate network isolation to the ASP.

INFO String: variable length

The optional INFO String parameter can carry any meaningful UTF-8 [10] character string along with the message. Length of the INFO String parameter is from 0 to 255 octets. No procedures are presently identified for its use but the INFO String MAY be used for debugging purposes.

#### 3.4.2 Destination Available (DAVA)

The DAVA message is sent from an SGP to all concerned ASPs to indicate that the SG has determined that one or more SS7 destinations are now reachable (and not restricted), or in response to a DAUD message if appropriate. If the ASP M3UA layer previously had no routes to the affected destinations the ASP MTP3-User protocol is informed and may now resume traffic to the affected destination. The ASP M3UA layer now routes the MTP3-user traffic through the SG initiating the DAVA message.

The DAVA message contains the following parameters:

Network Appearance	Optional
Routing Context	Optional
Affected Point Code	Mandatory
INFO String	Optional

The format and description of the Network Appearance, Routing Context, Affected Point Code and INFO String parameters is the same as for the DUNA message (See Section 3.4.1).

#### 3.4.3 Destination State Audit (DAUD)

The DAUD message MAY be sent from the ASP to the SGP to audit the availability/congestion state of SS7 routes from the SG to one or more affected destinations.

The DAUD message contains the following parameters:

Network Appearance	Optional
Routing Context	Optional
Affected Point Code	Mandatory
INFO String	Optional

The format and description of DAUD Message parameters is the same as for the DUNA message (See Section 3.4.1).


#### 3.4.4 Signalling Congestion (SCON)

The SCON message can be sent from an SGP to all concerned ASPs to indicate that an SG has determined that there is congestion in the SS7 network to one or more destinations, or to an ASP in response to a DATA or DAUD message as appropriate. For some MTP protocol variants (e.g., ANSI MTP) the SCON message may be sent when the SS7 congestion level changes. The SCON message MAY also be sent from the M3UA layer of an ASP to an M3UA peer indicating that the M3UA layer or the ASP is congested.

The SCON message contains the following parameters:

Network Appearance	Optional
Routing Context	Optional
Affected Point Code	Mandatory
Concerned Destination	Optional
Congestion Indications	Optional
INFO String	Optional

The format for SCON Message parameters is as follows:





The format and description of the Network Appearance, Routing Context, Affected Point Code, and INFO String parameters is the same as for the DUNA message (See Section 3.4.1).

The Affected Point Code parameter can be used to indicate congestion of multiple destinations or ranges of destinations.

Concerned Destination: 32-bits

The optional Concerned Destination parameter is only used if the SCON message is sent from an ASP to the SGP. It contains the point code of the originator of the message that triggered the SCON message. The Concerned Destination parameter contains one Concerned Destination Point Code field, a three-octet parameter to allow for 14-, 16- and 24-bit binary formatted SS7 Point Codes. A Concerned Point Code that is less than 24-bits is padded on the left to the 24-bit boundary. Any resulting Transfer Controlled (TFC) message from the SG is sent to the Concerned Point Code using the single Affected DPC contained in the SCON message to populate the (affected) Destination field of the TFC message

Congested Indications: 32-bits

The optional Congestion Indications parameter contains a Congestion Level field. This optional parameter is used to communicate congestion levels in national MTP networks with multiple congestion thresholds, such as in ANSI MTP3. For MTP congestion methods without multiple congestion levels (e.g., the ITU international method) the parameter is not included.

Congestion Level field: 8-bits (unsigned integer)

The Congestion Level field, associated with all of the Affected DPC(s) in the Affected Destinations parameter, contains one of the following values:

- |   |                            |
|---|----------------------------|
| 0 | No Congestion or Undefined |
| 1 | Congestion Level 1         |
| 2 | Congestion Level 2         |
| 3 | Congestion Level 3         |

The congestion levels are defined in the congestion method in the appropriate national MTP recommendations [7,8].


### 3.4.5 Destination User Part Unavailable (DUPU)

The DUPU message is used by an SGP to inform concerned ASPs that a remote peer MTP3-User Part (e.g., ISUP or SCCP) at an SS7 node is unavailable.

The DUPU message contains the following parameters:

Network Appearance	Optional
Routing Context	Optional
Affected Point Code	Mandatory
User/Cause	Mandatory
INFO String	Optional

The format for DUPU message parameters is as follows:



User/Cause: 32-bits

The Unavailability Cause and MTP3-User Identity fields, associated with the Affected PC in the Affected Point Code parameter, are encoded as follows:

Unavailability Cause field: 16-bits (unsigned integer)

The Unavailability Cause parameter provides the reason for the unavailability of the MTP3-User. The valid values for the Unavailability Cause parameter are shown in the following table. The values agree with those provided in the SS7 MTP3 User Part Unavailable message. Depending on the MTP3 protocol used in the Network Appearance, additional values may be used - the specification of the relevant MTP3 protocol variant/version recommendation is definitive.

0	Unknown
1	Unequipped Remote User
2	Inaccessible Remote User

MTP3-User Identity field: 16-bits (unsigned integer)

The MTP3-User Identity describes the specific MTP3-User that is unavailable (e.g., ISUP, SCCP, ...). Some of the valid values for the MTP3-User Identity are shown below. The values align with those provided in the SS7 MTP3 User Part Unavailable message and Service Indicator. Depending on the MTP3 protocol variant/version used in the network appearance, additional values may be used. The relevant MTP3 protocol variant/version recommendation is definitive.

0 to 2	Reserved
3	SCCP
4	TUP
5	ISUP
6 to 8	Reserved
9	Broadband ISUP
10	Satellite ISUP
11	Reserved
12	AAL type 2 Signalling
13	Bearer Independent Call Control (BICC)
14	Gateway Control Protocol
15	Reserved

The format and description of the Affected Point Code parameter is the same as for the DUNA message (See Section 3.4.1.) except that the Mask field is not used and only a single Affected DPC is

included. Ranges and lists of Affected DPCs cannot be signaled in a DUPU message, but this is consistent with UPU operation in the SS7 network. The Affected Destinations parameter in an MTP3 User Part Unavailable message (UPU) received by an SGP from the SS7 network contains only one destination.

The format and description of the Network Appearance, Routing Context, and INFO String parameters is the same as for the DUNA message (See Section 3.4.1).

#### 3.4.6 Destination Restricted (DRST)

The DRST message is optionally sent from the SGP to all concerned ASPs to indicate that the SG has determined that one or more SS7 destinations are now restricted from the point of view of the SG, or in response to a DAUD message if appropriate. The M3UA layer at the ASP is expected to send traffic to the affected destination via an alternate SG with route(s) of equal priority, but only if such an alternate route exists and is available. If the affected destination is currently considered unavailable by the ASP, The MTP3-User should be informed that traffic to the affected destination can be resumed. In this case, the M3UA layer should route the traffic through the SG initiating the DRST message.

This message is optional for the SG to send and it is optional for the ASP to act on any information received in the message. It is for use in the "STP" case described in Section 1.4.1.

The DRST message contains the following parameters:

Network Appearance	Optional
Routing Context	Optional
Affected Point Code	Mandatory
INFO String	Optional

The format and description of the Network Appearance, Routing Context, Affected Point Code and INFO String parameters is the same as for the DUNA message (See Section 3.4.1).

### 3.5 ASP State Maintenance (ASPSM) Messages

#### 3.5.1 ASP Up

The ASP Up message is used to indicate to a remote M3UA peer that the adaptation layer is ready to receive any ASPSM/ASPTM messages for all Routing Keys that the ASP is configured to serve.

The ASP Up message contains the following parameters:

ASP Identifier	Optional
INFO String	Optional

The format for ASP Up message parameters is as follows:

0																1																2																3																															
0	1	2	3	4	5	6	7	8	9	0	1	2	3	4	5	6	7	8	9	0	1	2	3	4	5	6	7	8	9	0	1	2	3	4	5	6	7	8	9																																								
																Tag = 0x0011																																Length = 8																															
																ASP Identifier																																																															
																Tag = 0x0004																																Length																															
\																																\																																\															
/																INFO String																/																																/															
\																																\																																\															

ASP Identifier: 32-bit unsigned integer

The optional ASP Identifier parameter contains a unique value that is locally significant among the ASPs that support an AS. The SGP should save the ASP Identifier to be used, if necessary, with the Notify message (see Section 3.8.2).

The format and description of the optional INFO String parameter is the same as for the DUNA message (See Section 3.4.1).


### 3.5.2 ASP Up Acknowledgement (ASP Up Ack)

The ASP UP Ack message is used to acknowledge an ASP Up message received from a remote M3UA peer.

The ASP Up Ack message contains the following parameters:

INFO String (optional)

The format for ASP Up Ack message parameters is as follows:



The format and description of the optional INFO String parameter is the same as for the DUNA message (See Section 3.4.1). The INFO String in an ASP Up Ack message is independent from the INFO String in the ASP Up message (i.e., it does not have to echo back the INFO String received).


### 3.5.3 ASP Down

The ASP Down message is used to indicate to a remote M3UA peer that the adaptation layer is NOT ready to receive DATA, SSNM, RKM or ASPTM messages.

The ASP Down message contains the following parameters:

INFO String      Optional

The format for the ASP Down message parameters is as follows:



The format and description of the optional INFO String parameter is the same as for the DUNA message (See Section 3.4.1).


#### 3.5.4 ASP Down Acknowledgement (ASP Down Ack)

The ASP Down Ack message is used to acknowledge an ASP Down message received from a remote M3UA peer.

The ASP Down Ack message contains the following parameters:

INFO String      Optional

The format for the ASP Down Ack message parameters is as follows:



The format and description of the optional INFO String parameter is the same as for the DUNA message (See Section 3.4.1).

The INFO String in an ASP Down Ack message is independent from the INFO String in the ASP Down message (i.e., it does not have to echo back the INFO String received).






The REG REQ message contains the following parameters:

Routing Key                      Mandatory

One or more Routing Key parameters MAY be included. The format for the REG REQ message is as follows:



Routing Key: variable length

The Routing Key parameter is mandatory. The sender of this message expects that the receiver of this message will create a Routing Key entry and assign a unique Routing Context value to it, if the Routing Key entry does not already exist.

The Routing Key parameter may be present multiple times in the same message. This is used to allow the registration of multiple Routing Keys in a single message.

The format of the Routing Key parameter is as follows.

[illegible]

Note: The Destination Point Code, Service Indicators, Originating Point Code List and Circuit Range List parameters MAY be repeated as a grouping within the Routing Key parameter, in the structure shown above.

Local-RK-Identifier: 32-bit unsigned integer

The mandatory Local-RK-Identifier field is used to uniquely identify the registration request. The Identifier value is assigned by the ASP, and is used to correlate the response in an REG RSP message with the original registration request. The Identifier value must remain unique until the REG RSP message is received.

The format of the Local-RK-Identifier field is as follows:

```

      0               1               2               3
      0 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1
+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+
|           Tag = 0x020a           |           Length = 8           |
+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+
|           Local-RK-Identifier value           |
+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+

```

Traffic Mode Type: 32-bit (unsigned integer)

The optional Traffic Mode Type parameter identifies the traffic mode of operation of the ASP(s) within an Application Server. The format of the Traffic Mode Type Identifier is as follows:

```

      0               1               2               3
      0 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1
+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+
|           Tag = 0x000b           |           Length = 8           |
+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+
|           Traffic Mode Type           |
+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+

```

The valid values for Traffic Mode Type are shown in the following table:

1	Override
2	Loadshare
3	Broadcast

Destination Point Code:

The Destination Point Code parameter is mandatory, and identifies the Destination Point Code of incoming SS7 traffic for which the ASP is registering. The format is the same as described for the Affected Destination parameter in the DUNA message (See Section 3.4.1). Its format is:

```

      0               1               2               3
      0 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1
+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+
|           Tag = 0x020b           |           Length = 8           |
+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+
|   Mask = 0   |           Destination Point Code           |
+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+

```

## Network Appearance:

The optional Network Appearance parameter field identifies the SS7 network context for the Routing Key, and has the same format as in the DATA message (See Section 3.3.1). The absence of the Network Appearance parameter in the Routing Key indicates the use of any Network Appearance value. Its format is:

```

      0               1               2               3
      0 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1
+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+
|           Tag = 0x0200           |           Length = 8           |
+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+
|           Network Appearance           |
+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+

```

## Service Indicators (SI): n X 8-bit integers

The optional SI [7,8] field contains one or more Service Indicators from the values as described in the MTP3-User Identity field of the DUPU message. The absence of the SI parameter in the Routing Key indicates the use of any SI value, excluding of course MTP management. Where an SI parameter does not contain a multiple of four SIs, the parameter is padded out to 32-byte alignment.

The SI format is:


```

      0               1               2               3
      0 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1
+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+
|           Tag = 0x020c           |           Length           |
+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+
|           SI #1           |           SI #2           |           SI #3           |           SI #4           |
+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+
/                               ...                               /
+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+
|           SI #n           |           0 Padding, if necessary           |
+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+

```

## OPC List:


The Originating Point Code List parameter contains one or more SS7 OPC entries, and its format is the same as the Destination Point Code parameter. The absence of the OPC List parameter in the Routing Key indicates the use of any OPC value,



#### Circuit Range:

An ISUP controlled circuit is uniquely identified by the SS7 OPC, DPC and CIC value. For the purposes of identifying Circuit Ranges in an M3UA Routing Key, the optional Circuit Range parameter includes one or more circuit ranges, each identified by an OPC and Upper/Lower CIC value. The DPC is implicit as it is mandatory and already included in the DPC parameter of the Routing Key. The absence of the Circuit Range parameter in the Routing Key indicates the use of any Circuit Range values, in the case of ISUP/TUP traffic. The Origination Point Code is encoded the same as the Destination Point Code parameter, while the CIC values are 16-bit integers.

The Circuit Range format is as follows:



### 3.6.2 Registration Response (REG RSP)

The REG RSP message is used as a response to the REG REQ message from a remote M3UA peer. It contains indications of success/failure for registration requests and returns a unique Routing Context value for successful registration requests, to be used in subsequent M3UA Traffic Management protocol.

The REG RSP message contains the following parameters:


Registration Result    Mandatory

One or more Registration Result parameters MUST be included. The format for the REG RSP message is as follows:



#### Registration Results:

The Registration Result parameter contains the registration result for a single Routing Key in an REG REQ message. The number of results in a single REG RSP message MUST be anywhere from one to the total number of number of Routing Key parameters found in the corresponding REG REQ message. Where multiple REG RSP messages are used in reply to REG REQ message, a specific result SHOULD be in only one REG RSP message. The format of each result is as follows:



#### Local-RK-Identifier: 32-bit integer

The Local-RK-Identifier contains the same value as found in the matching Routing Key parameter found in the REG REQ message (See Section 3.6.1).

Registration Status: 32-bit integer

The Registration Result Status field indicates the success or the reason for failure of a registration request.

Its values may be:

0	Successfully Registered
1	Error - Unknown
2	Error - Invalid DPC
3	Error - Invalid Network Appearance
4	Error - Invalid Routing Key
5	Error - Permission Denied
6	Error - Cannot Support Unique Routing
7	Error - Routing Key not Currently Provisioned
8	Error - Insufficient Resources
9	Error - Unsupported RK parameter Field
10	Error - Unsupported/Invalid Traffic Handling Mode

Routing Context: 32-bit integer

The Routing Context field contains the Routing Context value for the associated Routing Key if the registration was successful. It is set to "0" if the registration was not successful.

### 3.6.3 Deregistration Request (DEREG REQ)


The DEREG REQ message is sent by an ASP to indicate to a remote M3UA peer that it wishes to deregister a given Routing Key. Typically, an ASP would send this message to an SGP, and expects to receive a DEREG RSP message in return with the associated Routing Context value.

The DEREG REQ message contains the following parameters:

Routing Context	Mandatory
-----------------	-----------

The format for the DEREG REQ message is as follows:





Routing Context: n X 32-bit integers

The Routing Context parameter contains (a list of) integers indexing the Application Server traffic that the sending ASP is currently registered to receive from the SGP but now wishes to deregister.


#### 3.6.4 Deregistration Response (DEREG RSP)

The DEREG RSP message is used as a response to the DEREG REQ message from a remote M3UA peer.

The DEREG RSP message contains the following parameters:

Deregistration Result      Mandatory

One or more Deregistration Result parameters MUST be included. The format for the DEREG RSP message is as follows:



## Deregistration Results:

The Deregistration Result parameter contains the deregistration status for a single Routing Context in a DEREG REQ message. The number of results in a single DEREG RSP message MAY be anywhere from one to the total number of number of Routing Context values found in the corresponding DEREG REQ message.

Where multiple DEREG RSP messages are used in reply to DEREG REQ message, a specific result SHOULD be in only one DEREG RSP message. The format of each result is as follows:

```

      0                               1                               2                               3
      0 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1
+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+
|           Tag = 0x0006           |           Length = 8           |
+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+
|           Routing Context           |
+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+
|           Tag = 0x0213           |           Length = 8           |
+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+
|           Deregistration Status           |
+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+

```

Routing Context: 32-bit integer

The Routing Context field contains the Routing Context value of the matching Routing Key to deregister, as found in the DEREG REQ message.

Deregistration Status: 32-bit integer

The Deregistration Result Status field indicates the success or the reason for failure of the deregistration.

Its values may be:

- |   |  |
|---|--|
| 0 | Successfully Deregistered                        |
| 1 | Error - Unknown                                  |
| 2 | Error - Invalid Routing Context                  |
| 3 | Error - Permission Denied                        |
| 4 | Error - Not Registered                           |
| 5 | Error - ASP Currently Active for Routing Context |

### 3.7 ASP Traffic Maintenance (ASPTM) Messages

#### 3.7.1 ASP Active

The ASP Active message is sent by an ASP to indicate to a remote M3UA peer that it is ready to process signalling traffic for a particular Application Server. The ASP Active message affects only the ASP state for the Routing Keys identified by the Routing Contexts, if present.

The ASP Active message contains the following parameters:

Traffic Mode Type	Optional
Routing Context	Optional
INFO String	Optional

The format for the ASP Active message is as follows:

```

      0               1               2               3
      0 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1
+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+
|           Tag = 0x000b           |           Length = 8           |
+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+
|           Traffic Mode Type           |
+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+
|           Tag = 0x0006           |           Length           |
+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+
\                                     \
/                                     /
\                                     \
+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+
|           Tag = 0x0004           |           Length           |
+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+
\                                     \
/                                     /
\                                     \
+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+
|           INFO String           |
+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+---+

```

Traffic Mode Type: 32-bit (unsigned integer)

The Traffic Mode Type parameter identifies the traffic mode of operation of the ASP within an AS. The valid values for Traffic Mode Type are shown in the following table:

1	Override
2	Loadshare
3	Broadcast

Within a particular Routing Context, Override, Loadshare and Broadcast SHOULD NOT be mixed. The Override value indicates that the ASP is operating in Override mode, and the ASP takes over all traffic in an Application Server (i.e., primary/backup operation), overriding any currently active ASPs in the AS. In Loadshare mode, the ASP will share in the traffic distribution with any other currently active ASPs. In Broadcast mode, the ASP will receive the same messages as any other currently active ASP.

Routing Context: n X 32-bit integers

The optional Routing Context parameter contains (a list of) integers indexing the Application Server traffic that the sending ASP is configured/registered to receive.

There is one-to-one relationship between an index entry and an SGP Routing Key or AS Name. Because an AS can only appear in one Network Appearance, the Network Appearance parameter is not required in the ASP Active message.

An Application Server Process may be configured to process traffic for more than one logical Application Server. From the perspective of an ASP, a Routing Context defines a range of signalling traffic that the ASP is currently configured to receive from the SGP. For example, an ASP could be configured to support call processing for multiple ranges of PSTN trunks and therefore receive related signalling traffic, identified by separate SS7 DPC/OPC/CIC ranges.

The format and description of the optional INFO String parameter is the same as for the DUNA message (See Section 3.4.1).


### 3.7.2 ASP Active Acknowledgement (ASP Active Ack)

The ASP Active Ack message is used to acknowledge an ASP Active message received from a remote M3UA peer.

The ASP Active Ack message contains the following parameters:

Traffic Mode Type	Optional
Routing Context	Optional
INFO String	Optional

The format for the ASP Active Ack message is as follows:



The format and description of the optional INFO String parameter is the same as for the DUNA message (See Section 3.4.1).

The INFO String in an ASP Active Ack message is independent from the INFO String in the ASP Active message (i.e., it does not have to echo back the INFO String received).

The format of the Traffic Mode Type and Routing Context parameters is the same as for the ASP Active message. (See Section 3.7.1).


### 3.7.3 ASP Inactive

The ASP Inactive message is sent by an ASP to indicate to a remote M3UA peer that it is no longer an active ASP to be used from within a list of ASPs. The ASP Inactive message affects only the ASP state in the Routing Keys identified by the Routing Contexts, if present.

The ASP Inactive message contains the following parameters:

Routing Context	Optional
INFO String	Optional

The format for the ASP Inactive message parameters is as follows:



The format and description of the optional Routing Context and INFO String parameters is the same as for the ASP Active message (See Section 3.5.5.)


#### 3.7.4 ASP Inactive Acknowledgement (ASP Inactive Ack)

The ASP Inactive Ack message is used to acknowledge an ASP Inactive message received from a remote M3UA peer.

The ASP Inactive Ack message contains the following parameters:

Routing Context	Optional
INFO String	Optional

The format for the ASP Inactive Ack message is as follows:



The format and description of the optional INFO String parameter is the same as for the DUNA message (See Section 3.4.1.)

The INFO String in an ASP Inactive Ack message is independent from the INFO String in the ASP Inactive message (i.e., it does not have to echo back the INFO String received).

The format of the Routing Context parameter is the same as for the ASP Inactive message. (See Section 3.7.3).

### 3.8 Management (MGMT) Messages

#### 3.8.1 Error

The Error message is used to notify a peer of an error event associated with an incoming message. For example, the message type might be unexpected given the current state, or a parameter value might be invalid.

The Error message contains the following parameters:

Error Code	Mandatory
Routing Context	Mandatory*
Network Appearance	Mandatory*
Affected Point Code	Mandatory*
Diagnostic Information	Optional

(\*) Only mandatory for specific Error Codes

The format for the Error message is as follows:



Error Code: 32-bits (unsigned integer)

The Error Code parameter indicates the reason for the Error Message. The Error parameter value can be one of the following values:

0x01	Invalid Version
0x02	Not Used in M3UA
0x03	Unsupported Message Class
0x04	Unsupported Message Type
0x05	Unsupported Traffic Mode Type
0x06	Unexpected Message



0x07	Protocol Error
0x08	Not used in M3UA
0x09	Invalid Stream Identifier
0x0a	Not used in M3UA
0x0b	Not used in M3UA
0x0c	Not used in M3UA
0x0d	Refused - Management Blocking
0x0e	ASP Identifier Required
0x0f	Invalid ASP Identifier
0x10	Not Used in M3UA
0x11	Invalid Parameter Value
0x12	Parameter Field Error
0x13	Unexpected Parameter
0x14	Destination Status Unknown
0x15	Invalid Network Appearance
0x16	Missing Parameter
0x17	Not Used in M3UA
0x18	Not Used in M3UA
0x19	Invalid Routing Context
0x1a	No Configured AS for ASP

The "Invalid Stream Identifier" error is sent if a message is received on an unexpected SCTP stream (e.g., a MGMT message was received on a stream other than "0"). Error messages MUST NOT be generated in response to other Error messages.

The "Unsupported Message Class" error is sent if a message with an unexpected or unsupported Message Class is received.

The "Unsupported Message Type" error is sent if a message with an unexpected or unsupported Message Type is received.

The "Unsupported Traffic Mode Type" error is sent by a SGP if an ASP sends an ASP Active message with an unsupported Traffic Mode Type or a Traffic Mode Type that is inconsistent with the presently configured mode for the Application Server. An example would be a case in which the SGP did not support loadsharing.

The "Unexpected Message" error MAY be sent if a defined and recognized message is received that is not expected in the current state (in some cases the ASP may optionally silently discard the message and not send an Error message). For example, silent discard is used by an ASP if it received a DATA message from an SGP while it was in the ASP-INACTIVE state. If the Unexpected message contained Routing Context(s), the Routing Context(s) SHOULD be included in the Error message.

The "Protocol Error" error is sent for any protocol anomaly (i.e., reception of a parameter that is syntactically correct but unexpected in the current situation).

The "Invalid Stream Identifier" error is sent if a message is received on an unexpected SCTP stream (e.g., a Management message was received on a stream other than "0").

The "Refused - Management Blocking" error is sent when an ASP Up or ASP Active message is received and the request is refused for management reasons (e.g., management lockout). If this error is in response to an ASP Active message, the Routing Context(s) in the ASP Active message SHOULD be included in the Error message.

The "ASP Identifier Required" is sent by a SGP in response to an ASP Up message which does not contain an ASP Identifier parameter when the SGP requires one. The ASP SHOULD resend the ASP Up message with an ASP Identifier.

The "Invalid ASP Identifier" is sent by an SGP in response to an ASP Up message with an invalid (i.e., non-unique) ASP Identifier.

The "Invalid Parameter Value " error is sent if a message is received with an invalid parameter value (e.g., a DUPU message was received with a Mask value other than "0").

The "Parameter Field Error" would be sent if a message is received with a parameter having a wrong length field.

The "Unexpected Parameter" error would be sent if a message contains an invalid parameter.

The "Destination Status Unknown" Error MAY be sent if a DAUD is received at an SG enquiring of the availability/congestion status of a destination, and the SG does not wish to provide the status (e.g., the sender is not authorized to know the status). For this error, the invalid or unauthorized Point Code(s) MUST be included along with the Network Appearance and/or Routing Context associated with the Point Code(s).

The "Invalid Network Appearance" error is sent by a SGP if an ASP sends a message with an invalid (unconfigured) Network Appearance value. For this error, the invalid (unconfigured) Network Appearance MUST be included in the Network Appearance parameter.

The "Missing Parameter" error would be sent if a mandatory parameter were not included in a message.

The "Invalid Routing Context" error is sent if a message is received from a peer with an invalid (unconfigured) Routing Context value. For this error, the invalid Routing Context(s) MUST be included in the Error message.

The "No Configured AS for ASP" error is sent if a message is received from a peer without a Routing Context parameter and it is not known by configuration data which Application Servers are referenced.

Diagnostic Information: variable length

When included, the optional Diagnostic information can be any information germane to the error condition, to assist in identification of the error condition. The Diagnostic information SHOULD contain the offending message.


### 3.8.2 Notify

The Notify message used to provide an autonomous indication of M3UA events to an M3UA peer.

The Notify message contains the following parameters:

Status	Mandatory
ASP Identifier	Optional
Routing Context	Optional
INFO String	Optional

The format for the Notify message is as follows:



Status Type: 16-bits (unsigned integer)

The Status Type parameter identifies the type of the Notify message. The following are the valid Status Type values:

- 1 Application Server State Change (AS-State\_Change)
- 2 Other

Status Information: 16-bits (unsigned integer)

The Status Information parameter contains more detailed information for the notification, based on the value of the Status Type. If the Status Type is AS-State\_Change the following Status Information values are used:

- 1 reserved
- 2 Application Server Inactive (AS-INACTIVE)
- 3 Application Server Active (AS-ACTIVE)
- 4 Application Server Pending (AS-PENDING)

These notifications are sent from an SGP to an ASP upon a change in status of a particular Application Server. The value reflects the new state of the Application Server.

If the Status Type is Other, then the following Status Information values are defined:

- 1      Insufficient ASP Resources Active in AS
- 2      Alternate ASP Active
- 3      ASP Failure

These notifications are not based on the SGP reporting the state change of an ASP or AS. In the Insufficient ASP Resources case, the SGP is indicating to an ASP\_INACTIVE ASP in the AS that another ASP is required to handle the load of the AS (Loadsharing or Broadcast mode). For the Alternate ASP Active case, an ASP is informed when an alternate ASP transitions to the ASP-ACTIVE state in Override mode. The ASP Identifier (if available) of the Alternate ASP MUST be placed in the message. For the ASP Failure case, the SGP is indicating to ASP(s) in the AS that one of the ASPs has transitioned to ASP-DOWN. The ASP Identifier (if available) of the failed ASP MUST be placed in the message.

The format and description of the optional ASP Identifier is the same as for the ASP Up message (See Section 3.5.1). The format and description of the Routing Context and Info String parameters is the same as for the ASP Active message (See Section 3.7.1)

#### 4. Procedures

The M3UA layer needs to respond to various local primitives it receives from other layers as well as the messages that it receives from the peer M3UA layer. This section describes the M3UA procedures in response to these events.

##### 4.1 Procedures to Support the M3UA-User

###### 4.1.1 Receipt of Primitives from the M3UA-User

On receiving an MTP-TRANSFER request primitive from an upper layer at an ASP/IPSP, or the nodal interworking function at an SGP, the M3UA layer sends a corresponding DATA message (see Section 3) to its M3UA peer. The M3UA peer receiving the DATA message sends an MTP-TRANSFER indication primitive to the upper layer.

The M3UA message distribution function (see Section 1.4.2.1) determines the Application Server (AS) based on comparing the information in the MTP-TRANSFER request primitive with a provisioned Routing Key.

From the list of ASPs within the AS table, an ASP in the ASP-ACTIVE state is selected and a DATA message is constructed and issued on the corresponding SCTP association. If more than one ASP is in the ASP-ACTIVE state (i.e., traffic is to be loadshared across more than one ASP), one of the ASPs in the ASP-ACTIVE state is selected from the list. If the ASPs are in Broadcast Mode, all active ASPs will be selected and the message sent to each of the active ASPs. The selection algorithm is implementation dependent but could, for example, be round robin or based on the SLS or ISUP CIC. The appropriate selection algorithm must be chosen carefully as it is dependent on application assumptions and understanding of the degree of state coordination between the ASP-ACTIVE ASPs in the AS.

In addition, the message needs to be sent on the appropriate SCTP stream, again taking care to meet the message sequencing needs of the signalling application. DATA messages MUST be sent on an SCTP stream other than stream '0'.

When there is no Routing Key match, or only a partial match, for an incoming SS7 message, a default treatment MAY be specified. Possible solutions are to provide a default Application Server at the SGP that directs all unallocated traffic to a (set of) default ASP(s), or to drop the message and provide a notification to Layer Management in an M-ERROR indication primitive. The treatment of unallocated traffic is implementation dependent.

#### 4.2 Receipt of Primitives from the Layer Management

On receiving primitives from the local Layer Management, the M3UA layer will take the requested action and provide an appropriate response primitive to Layer Management.

An M-SCTP\_ESTABLISH request primitive from Layer Management at an ASP or IPSP will initiate the establishment of an SCTP association. The M3UA layer will attempt to establish an SCTP association with the remote M3UA peer by sending an SCTP-ASSOCIATE primitive to the local SCTP layer.

When an SCTP association has been successfully established, the SCTP will send an SCTP-COMMUNICATION\_UP notification primitive to the local M3UA layer. At the SGP or IPSP that initiated the request, the M3UA layer will send an M-SCTP\_ESTABLISH confirm primitive to Layer Management when the association setup is complete. At the peer M3UA

layer, an M-SCTP\_ESTABLISH indication primitive is sent to Layer Management upon successful completion of an incoming SCTP association setup.

An M-SCTP\_RELEASE request primitive from Layer Management initiates the teardown of an SCTP association. The M3UA layer accomplishes a graceful shutdown of the SCTP association by sending an SCTP\_SHUTDOWN primitive to the SCTP layer.

When the graceful shutdown of the SCTP association has been accomplished, the SCTP layer returns an SCTP\_SHUTDOWN\_COMPLETE notification primitive to the local M3UA layer. At the M3UA Layer that initiated the request, the M3UA layer will send an M-SCTP\_RELEASE confirm primitive to Layer Management when the association shutdown is complete. At the peer M3UA Layer, an M-SCTP\_RELEASE indication primitive is sent to Layer Management upon abort or successful shutdown of an SCTP association.

An M-SCTP\_STATUS request primitive supports a Layer Management query of the local status of a particular SCTP association. The M3UA layer simply maps the M-SCTP\_STATUS request primitive to an SCTP\_STATUS primitive to the SCTP layer. When the SCTP responds, the M3UA layer maps the association status information to an M-SCTP\_STATUS confirm primitive. No peer protocol is invoked.

Similar LM-to-M3UA-to-SCTP and/or SCTP-to-M3UA-to-LM primitive mappings can be described for the various other SCTP Upper Layer primitives in RFC2960 [17] such as INITIALIZE, SET PRIMARY, CHANGE HEARTBEAT, REQUEST HEARTBEAT, GET SRTT REPORT, SET FAILURE THRESHOLD, SET PROTOCOL PARAMETERS, DESTROY SCTP INSTANCE, SEND FAILURE, AND NETWORK STATUS CHANGE. Alternatively, these SCTP Upper Layer primitives (and Status as well) can be considered for modeling purposes as a Layer Management interaction directly with the SCTP Layer.

M-NOTIFY indication and M-ERROR indication primitives indicate to Layer Management the notification or error information contained in a received M3UA Notify or Error message respectively. These indications can also be generated based on local M3UA events.

An M-ASP\_STATUS request primitive supports a Layer Management query of the status of a particular local or remote ASP. The M3UA layer responds with the status in an M-ASP\_STATUS confirm primitive. No M3UA peer protocol is invoked.

An M-AS\_STATUS request supports a Layer Management query of the status of a particular AS. The M3UA responds with an M-AS\_STATUS confirm primitive. No M3UA peer protocol is invoked.

M-ASP\_UP request, M-ASP\_DOWN request, M-ASP\_ACTIVE request and M-ASP\_INACTIVE request primitives allow Layer Management at an ASP to initiate state changes. Upon successful completion, a corresponding confirm primitive is provided by the M3UA layer to Layer Management. If an invocation is unsuccessful, an Error indication primitive is provided in the primitive. These requests result in outgoing ASP Up, ASP Down, ASP Active and ASP Inactive messages to the remote M3UA peer at an SGP or IPSP.

#### 4.2.1 Receipt of M3UA Peer Management Messages

Upon successful state changes resulting from reception of ASP Up, ASP Down, ASP Active and ASP Inactive messages from a peer M3UA, the M3UA layer MAY invoke corresponding M-ASP\_UP, M-ASP\_DOWN, M-ASP\_ACTIVE and M-ASP\_INACTIVE, M-AS\_ACTIVE, M-AS\_INACTIVE, and M-AS\_DOWN indication primitives to the local Layer Management.

M-NOTIFY indication and M-ERROR indication primitives indicate to Layer Management the notification or error information contained in a received M3UA Notify or Error message. These indications can also be generated based on local M3UA events.

All non-Transfer and non-SSNM, messages, except BEAT and BEAT Ack, SHOULD be sent with sequenced delivery to ensure ordering. ASPTM messages MAY be sent on one of the streams used to carry the data traffic related to the Routing Context(s), to minimize possible message loss. BEAT and BEAT Ack messages MAY be sent using out-of-order delivery, and MAY be sent on any stream.

#### 4.3 AS and ASP State Maintenance

The M3UA layer on the SGP maintains the state of each remote ASP, in each Application Server that the ASP is configured to receive traffic, as input to the M3UA message distribution function. Similarly, where IPSPs use M3UA in a point-to-point fashion, the M3UA layer in an IPSP maintains the state of remote IPSPs. For the purposes of the following procedures, only the SGP/ASP case is described but the SGP side of the procedures also apply to an IPSP sending traffic to an AS consisting of a set of remote IPSPs.



#### 4.3.1 ASP States

The state of each remote ASP, in each AS that it is configured to operate, is maintained in the M3UA layer in the SGP. The state of a particular ASP in a particular AS changes due to events. The events include:

- \* Reception of messages from the peer M3UA layer at the ASP;
- \* Reception of some messages from the peer M3UA layer at other ASPs in the AS (e.g., ASP Active message indicating "Override");
- \* Reception of indications from the SCTP layer; or
- \* Local Management intervention.

The ASP state transition diagram is shown in Figure 3. The possible states of an ASP are:

**ASP-DOWN:** The remote M3UA peer at the ASP is unavailable and/or the related SCTP association is down. Initially all ASPs will be in this state. An ASP in this state SHOULD NOT be sent any M3UA messages, with the exception of Heartbeat, ASP Down Ack and Error messages.


**ASP-INACTIVE:** The remote M3UA peer at the ASP is available (and the related SCTP association is up) but application traffic is stopped. In this state the ASP SHOULD NOT be sent any DATA or SSNM messages for the AS for which the ASP is inactive.

**ASP-ACTIVE:** The remote M3UA peer at the ASP is available and application traffic is active (for a particular Routing Context or set of Routing Contexts).

**SCTP CDI:** The SCTP CDI denotes the local SCTP layer's Communication Down Indication to the Upper Layer Protocol (M3UA) on an SGP. The local SCTP layer will send this indication when it detects the loss of connectivity to the ASP's peer SCTP layer. SCTP CDI is understood as either a SHUTDOWN\_COMPLETE notification or COMMUNICATION\_LOST notification from the SCTP layer.

**SCTP RI:** The local SCTP layer's Restart indication to the upper layer protocol (M3UA) on an SG. The local SCTP will send this indication when it detects a restart from the ASP's peer SCTP layer.

Figure 3: ASP State Transition Diagram, per AS



#### 4.3.2 AS States

The state of the AS is maintained in the M3UA layer on the SGPs. The state of an AS changes due to events. These events include:

- \* ASP state transitions
- \* Recovery timer triggers

The possible states of an AS are:

**AS-DOWN:** The Application Server is unavailable. This state implies that all related ASPs are in the ASP-DOWN state for this AS. Initially the AS will be in this state. An Application Server is in the AS-DOWN state when it is removed from a configuration.

**AS-INACTIVE:** The Application Server is available but no application traffic is active (i.e., one or more related ASPs are in the ASP-INACTIVE state, but none in the ASP-ACTIVE state). The recovery timer  $T(r)$  is not running or has expired.

AS-ACTIVE: The Application Server is available and application traffic is active. This state implies that at least one ASP is in the ASP-ACTIVE state.


AS-PENDING: An active ASP has transitioned to ASP-INACTIVE or ASP-DOWN and it was the last remaining active ASP in the AS. A recovery timer  $T(r)$  SHOULD be started and all incoming signalling messages SHOULD be queued by the SGP. If an ASP becomes ASP-ACTIVE before  $T(r)$  expires, the AS is moved to the AS-ACTIVE state and all the queued messages will be sent to the ASP.

If  $T(r)$  expires before an ASP becomes ASP-ACTIVE, and the SGP has no alternative, the SGP may stop queuing messages and discards all previously queued messages. The AS will move to the AS-INACTIVE state.

If at least one ASP is in ASP-INACTIVE state, otherwise it will move to AS-DOWN state.

Figure 4 shows an example AS state machine for the case where the AS/ASP data is preconfigured. For other cases where the AS/ASP configuration data is created dynamically, there would be differences in the state machine, especially at creation of the AS.

Figure 4: AS State Transition Diagram



Tr = Recovery Timer

For example, where the AS/ASP configuration data is not created until Registration of the first ASP, the AS-INACTIVE state is entered directly upon the first successful REG REQ from an ASP. Another example is where the AS/ASP configuration data is not created until the first ASP successfully enters the ASP-ACTIVE state. In this case the AS-ACTIVE state is entered directly.

#### 4.3.3 M3UA Management Procedures for Primitives

Before the establishment of an SCTP association the ASP state at both the SGP and ASP is assumed to be in the state ASP-DOWN.

Once the SCTP association is established (see Section 4.2) and assuming that the local M3UA-User is ready, the local M3UA ASP Maintenance (ASPM) function will initiate the relevant procedures, using the ASP Up/ASP Down/ASP Active/ASP Inactive messages to convey the ASP state to the SGP (see Section 4.3.4).

If the M3UA layer subsequently receives an SCTP-COMMUNICATION\_DOWN or SCTP-RESTART indication primitive from the underlying SCTP layer, it will inform the Layer Management by invoking the M-SCTP\_STATUS indication primitive. The state of the ASP will be moved to ASP-DOWN. At an ASP, the MTP3-User will be informed of the unavailability of any affected SS7 destinations through the use of MTP-PAUSE indication primitives.

In the case of SCTP-COMMUNICATION\_DOWN, the SCTP client MAY try to re-establish the SCTP Association. This MAY be done by the M3UA layer automatically, or Layer Management MAY re-establish using the M-SCTP\_ESTABLISH request primitive.

In the case of an SCTP-RESTART indication at an ASP, the ASP is now considered by its M3UA peer to be in the ASP-DOWN state. The ASP, if it is to recover, must begin any recovery with the ASP-Up procedure.

#### 4.3.4 ASPM Procedures for Peer-to-Peer Messages

##### 4.3.4.1 ASP Up Procedures

After an ASP has successfully established an SCTP association to an SGP, the SGP waits for the ASP to send an ASP Up message, indicating that the ASP M3UA peer is available. The ASP is always the initiator of the ASP Up message. This action MAY be initiated at the ASP by an M-ASP\_UP request primitive from Layer Management or MAY be initiated automatically by an M3UA management function.

When an ASP Up message is received at an SGP and internally the remote ASP is in the ASP-DOWN state and not considered locked out for local management reasons, the SGP marks the remote ASP in the state ASP-INACTIVE and informs Layer Management with an M-ASP\_Up indication primitive. If the SGP is aware, via current configuration data, which Application Servers the ASP is configured to operate in, the SGP updates the ASP state to ASP-INACTIVE in each AS that it is a member.

Alternatively, the SGP may move the ASP into a pool of Inactive ASPs available for future configuration within Application Server(s), determined in a subsequent Registration Request or ASP Active procedure. If the ASP Up message contains an ASP Identifier, the SGP should save the ASP Identifier for that ASP. The SGP MUST send an ASP Up Ack message in response to a received ASP Up message even if the ASP is already marked as ASP-INACTIVE at the SGP.

If for any local reason (e.g., management lockout) the SGP cannot respond with an ASP Up Ack message, the SGP responds to an ASP Up message with an Error message with reason "Refused - Management Blocking".

At the ASP, the ASP Up Ack message received is not acknowledged. Layer Management is informed with an M-ASP\_UP confirm primitive.

When the ASP sends an ASP Up message it starts timer T(ack). If the ASP does not receive a response to an ASP Up message within T(ack), the ASP MAY restart T(ack) and resend ASP Up messages until it receives an ASP Up Ack message. T(ack) is provisionable, with a default of 2 seconds. Alternatively, retransmission of ASP Up messages MAY be put under control of Layer Management. In this method, expiry of T(ack) results in an M-ASP\_UP confirm primitive carrying a negative indication.

The ASP must wait for the ASP Up Ack message before sending any other M3UA messages (e.g., ASP Active or REG REQ). If the SGP receives any other M3UA messages before an ASP Up message is received (other than ASP Down - see Section 4.3.4.2), the SGP MAY discard them.

If an ASP Up message is received and internally the remote ASP is in the ASP-ACTIVE state, an ASP Up Ack message is returned, as well as an Error message ("Unexpected Message), and the remote ASP state is changed to ASP-INACTIVE in all relevant Application Servers.

If an ASP Up message is received and internally the remote ASP is already in the ASP-INACTIVE state, an ASP Up Ack message is returned and no further action is taken.

#### 4.3.4.1.1 M3UA Version Control

If an ASP Up message with an unsupported version is received, the receiving end responds with an Error message, indicating the version the receiving node supports and notifies Layer Management.

This is useful when protocol version upgrades are being performed in a network. A node upgraded to a newer version should support the older versions used on other nodes it is communicating with. Because ASPs initiate the ASP Up procedure it is assumed that the Error message would normally come from the SGP.

#### 4.3.4.1.2 IPSP Considerations (ASP Up)

An IPSP may be considered in the ASP-INACTIVE state after an ASP Up or ASP Up Ack has been received from it. An IPSP can be considered in the ASP-DOWN state after an ASP Down or ASP Down Ack has been received from it. The IPSP may inform Layer Management of the change in state of the remote IPSP using M-ASP\_UP or M-ASP\_DN indication or confirmation primitives.

Alternatively, an interchange of ASP Up messages from each end can be performed. This option follows the ASP state transition diagram. It would need four messages for completion.

If for any local reason (e.g., management lockout) an IPSP cannot respond to an ASP Up message with an ASP Up Ack message, it responds to an ASP Up message with an Error message with reason "Refused Management Blocking" and leaves the remote IPSP in the ASP-DOWN state.

#### 4.3.4.2 ASP-Down Procedures

The ASP will send an ASP Down message to an SGP when the ASP wishes to be removed from service in all Application Servers that it is a member and no longer receive any DATA, SSNM or ASPTM messages. This action MAY be initiated at the ASP by an M-ASP\_DOWN request primitive from Layer Management or MAY be initiated automatically by an M3UA management function.

Whether the ASP is permanently removed from any AS is a function of configuration management. In the case where the ASP previously used the Registration procedures (see Section 4.4.1) to register within Application Servers but has not deregistered from all of them prior to sending the ASP Down message, the SGP MUST consider the ASP as Deregistered in all Application Servers that it is still a member.

The SGP marks the ASP as ASP-DOWN, informs Layer Management with an M-ASP\_Down indication primitive, and returns an ASP Down Ack message to the ASP.

The SGP MUST send an ASP Down Ack message in response to a received ASP Down message from the ASP even if the ASP is already marked as ASP-DOWN at the SGP.

At the ASP, the ASP Down Ack message received is not acknowledged. Layer Management is informed with an M-ASP\_DOWN confirm primitive. If the ASP receives an ASP Down Ack without having sent an ASP Down message, the ASP should now consider itself as in the ASP-DOWN state.

If the ASP was previously in the ASP-ACTIVE or ASP-INACTIVE state, the ASP should then initiate procedures to return itself to its previous state.

When the ASP sends an ASP Down message it starts timer T(ack). If the ASP does not receive a response to an ASP Down message within T(ack), the ASP MAY restart T(ack) and resend ASP Down messages until it receives an ASP Down Ack message. T(ack) is provisionable, with a default of 2 seconds. Alternatively, retransmission of ASP Down messages MAY be put under control of Layer Management. In this method, expiry of T(ack) results in an M-ASP\_DOWN confirm primitive carrying a negative indication.

#### 4.3.4.3 ASP Active Procedures

Anytime after the ASP has received an ASP Up Ack message from the SGP or IPSP, the ASP MAY send an ASP Active message to the SGP indicating that the ASP is ready to start processing traffic. This action MAY be initiated at the ASP by an M-ASP\_ACTIVE request primitive from Layer Management or MAY be initiated automatically by an M3UA management function. In the case where an ASP wishes to process the traffic for more than one Application Server across a common SCTP association, the ASP Active message(s) SHOULD contain a list of one or more Routing Contexts to indicate for which Application Servers the ASP Active message applies. It is not necessary for the ASP to include all Routing Contexts of interest in a single ASP Active message, thus requesting to become active in all Routing Contexts at the same time. Multiple ASP Active messages MAY be used to activate within the Application Servers independently, or in sets. In the case where an ASP Active message does not contain a Routing Context parameter, the receiver must know, via configuration data, which Application Server(s) the ASP is a member.

For the Application Servers that the ASP can be successfully activated, the SGP or IPSP responds with one or more ASP Active Ack messages, including the associated Routing Context(s) and reflecting any Traffic Mode Type value present in the related ASP Active message. The Routing Context parameter MUST be included in the ASP Active Ack message(s) if the received ASP Active message contained any Routing Contexts. Depending on any Traffic Mode Type request in the ASP Active message, or local configuration data if there is no request, the SGP moves the ASP to the correct ASP traffic state within the associated Application Server(s). Layer Management is informed with an M-ASP\_Active indication. If the SGP or IPSP receives any Data messages before an ASP Active message is received, the SGP or IPSP MAY discard them. By sending an ASP Active Ack message, the SGP or IPSP is now ready to receive and send traffic for the related



Routing Context(s). The ASP SHOULD NOT send Data or SSNM messages for the related Routing Context(s) before receiving an ASP Active Ack message, or it will risk message loss.

Multiple ASP Active Ack messages MAY be used in response to an ASP Active message containing multiple Routing Contexts, allowing the SGP or IPSP to independently acknowledge the ASP Active message for different (sets of) Routing Contexts. The SGP or IPSP MUST send an Error message ("Invalid Routing Context") for each Routing Context value that the ASP cannot be successfully activated .

In the case where an "out-of-the-blue" ASP Active message is received (i.e., the ASP has not registered with the SG or the SG has no static configuration data for the ASP), the message MAY be silently discarded.

The SGP MUST send an ASP Active Ack message in response to a received ASP Active message from the ASP, if the ASP is already marked in the ASP-ACTIVE state at the SGP.

At the ASP, the ASP Active Ack message received is not acknowledged. Layer Management is informed with an M-ASP\_ACTIVE confirm primitive. It is possible for the ASP to receive Data message(s) before the ASP Active Ack message as the ASP Active Ack and Data messages from an SG or IPSP may be sent on different SCTP streams. Message loss is possible as the ASP does not consider itself in the ASP-ACTIVE state until reception of the ASP Active Ack message.

When the ASP sends an ASP Active message it starts timer T(ack). If the ASP does not receive a response to an ASP Active message within T(ack), the ASP MAY restart T(ack) and resend ASP Active messages until it receives an ASP Active Ack message. T(ack) is provisionable, with a default of 2 seconds. Alternatively, retransmission of ASP Active messages MAY be put under control of Layer Management. In this method, expiry of T(ack) results in an M-ASP\_ACTIVE confirm primitive carrying a negative indication.

There are three modes of Application Server traffic handling in the SGP M3UA layer: Override, Loadshare and Broadcast. When included, the Traffic Mode Type parameter in the ASP Active message indicates the traffic handling mode to be used in a particular Application Server. If the SGP determines that the mode indicated in an ASP Active message is unsupported or incompatible with the mode currently configured for the AS, the SGP responds with an Error message ("Unsupported / Invalid Traffic Handling Mode"). If the traffic handling mode of the Application Server is not already known via

configuration data, then the traffic handling mode indicated in the first ASP Active message causing the transition of the Application Server state to AS-ACTIVE MAY be used to set the mode.

In the case of an Override mode AS, reception of an ASP Active message at an SGP causes the (re)direction of all traffic for the AS to the ASP that sent the ASP Active message. Any previously active ASP in the AS is now considered to be in state ASP-INACTIVE and SHOULD no longer receive traffic from the SGP within the AS. The SGP or IPSP then MUST send a Notify message ("Alternate ASP\_Active") to the previously active ASP in the AS, and SHOULD stop traffic to/from that ASP. The ASP receiving this Notify MUST consider itself now in the ASP-INACTIVE state, if it is not already aware of this via inter-ASP communication with the Overriding ASP.

In the case of a Loadshare mode AS, reception of an ASP Active message at an SGP or IPSP causes the direction of traffic to the ASP sending the ASP Active message, in addition to all the other ASPs that are currently active in the AS. The algorithm at the SGP for loadsharing traffic within an AS to all the active ASPs is implementation dependent. The algorithm could, for example, be round-robin or based on information in the Data message (e.g., the SLS, SCCP SSN, ISUP CIC value).

An SGP or IPSP, upon reception of an ASP Active message for the first ASP in a Loadshare AS, MAY choose not to direct traffic to a newly active ASP until it determines that there are sufficient resources to handle the expected load (e.g., until there are "n" ASPs in state ASP-ACTIVE in the AS). In this case, the SGP or IPSP SHOULD withhold the Notify (AS-ACTIVE) until there are sufficient resources.

For the n+k redundancy case, ASPs which are in that AS should coordinate among themselves the number of active ASPs in the AS, and should start sending traffic only after n ASPs are active.

All ASPs within a loadsharing mode AS must be able to process any Data message received for the AS, to accommodate any potential failover or rebalancing of the offered load.

In the case of a Broadcast mode AS, reception of an ASP Active message at an SGP or IPSP causes the direction of traffic to the ASP sending the ASP Active message, in addition to all the other ASPs that are currently active in the AS. The algorithm at the SGP for broadcasting traffic within an AS to all the active ASPs is a simple broadcast algorithm, where every message is sent to each of the active ASPs.

An SGP or IPSP, upon reception of an ASP Active message for the first ASP in a Broadcast AS, MAY choose not to direct traffic to a newly active ASP until it determines that there are sufficient resources to handle the expected load (e.g., until there are "n" ASPs in state ASP-ACTIVE in the AS). In this case, the SGP or IPSP SHOULD withhold the Notify (AS-ACTIVE) until there are sufficient resources.

For the n+k redundancy case, ASPs which are in that AS should coordinate among themselves the number of active ASPs in the AS, and should start sending traffic only after n ASPs are active.

Whenever an ASP in a Broadcast mode AS becomes ASP-ACTIVE, the SGP MUST tag the first DATA message broadcast in each traffic flow with

a unique Correlation Id parameter. The purpose of this Id is to permit the newly active ASP to synchronize its processing of traffic in each traffic flow with the other ASPs in the broadcast group.

#### 4.3.4.3.1 IPSP Considerations (ASP Active)

Either of the IPSPs can initiate communication. When an IPSP receives an ASP Active, it should mark the peer as ASP-ACTIVE and return an ASP Active Ack message. An ASP receiving an ASP Active Ack message may mark the peer as ASP-Active, if it is not already in the ASP-ACTIVE state.

Alternatively, an interchange of ASP Active messages from each end can be performed. This option follows the ASP state transition diagram and gives the additional advantage of selecting a particular AS to be activated from each end. It is especially useful when an IPSP is serving more than one AS. It would need four messages for completion.

#### 4.3.4.4 ASP Inactive Procedures

When an ASP wishes to withdraw from receiving traffic within an AS, the ASP sends an ASP Inactive message to the SGP or IPSP. This action MAY be initiated at the ASP by an M-ASP\_INACTIVE request primitive from Layer Management or MAY be initiated automatically by an M3UA management function. In the case where an ASP is processing the traffic for more than one Application Server across a common SCTP association, the ASP Inactive message contains one or more Routing Contexts to indicate for which Application Servers the ASP Inactive message applies. In the case where an ASP Inactive message does not contain a Routing Context parameter, the receiver must know, via configuration data, which Application Servers the ASP is a member and move the ASP to the ASP-INACTIVE state in all Application Servers. In the case of an Override mode AS, where another ASP has already taken

over the traffic within the AS with an ASP Active ("Override") message, the ASP that sends the ASP Inactive message is already considered by the SGP to be in state ASP-INACTIVE. An ASP Inactive Ack message is sent to the ASP, after ensuring that all traffic is stopped to the ASP.

In the case of a Loadshare mode AS, the SGP moves the ASP to the ASP-INACTIVE state and the AS traffic is reallocated across the remaining ASPs in the state ASP-ACTIVE, as per the loadsharing algorithm currently used within the AS. A Notify message ("Insufficient ASP resources active in AS") MAY be sent to all inactive ASPs, if required. An ASP Inactive Ack message is sent to the ASP after all traffic is halted and Layer Management is informed with an M-ASP\_INACTIVE indication primitive.

In the case of a Broadcast mode AS, the SGP moves the ASP to the ASP-INACTIVE state and the AS traffic is broadcast only to the remaining ASPs in the state ASP-ACTIVE. A Notify message ("Insufficient ASP resources active in AS") MAY be sent to all inactive ASPs, if required. An ASP Inactive Ack message is sent to the ASP after all traffic is halted and Layer Management is informed with an M-ASP\_INACTIVE indication primitive.

Multiple ASP Inactive Ack messages MAY be used in response to an ASP Inactive message containing multiple Routing Contexts, allowing the SGP or IPSP to independently acknowledge for different (sets of) Routing Contexts. The SGP or IPSP sends an Error message ("Invalid Routing Context") message for each invalid or unconfigured Routing Context value in a received ASP Inactive message.

The SGP MUST send an ASP Inactive Ack message in response to a received ASP Inactive message from the ASP and the ASP is already marked as ASP-INACTIVE at the SGP.

At the ASP, the ASP Inactive Ack message received is not acknowledged. Layer Management is informed with an M-ASP\_INACTIVE confirm primitive. If the ASP receives an ASP Inactive Ack without having sent an ASP Inactive message, the ASP should now consider itself as in the ASP-INACTIVE state. If the ASP was previously in the ASP-ACTIVE state, the ASP should then initiate procedures to return itself to its previous state.

When the ASP sends an ASP Inactive message it starts timer T(ack). If the ASP does not receive a response to an ASP Inactive message within T(ack), the ASP MAY restart T(ack) and resend ASP Inactive messages until it receives an ASP Inactive Ack message. T(ack) is provisionable, with a default of 2 seconds. Alternatively,

retransmission of ASP Inactive messages MAY be put under control of Layer Management. In this method, expiry of T(ack) results in a M-ASP\_Inactive confirm primitive carrying a negative indication.

If no other ASPs in the Application Server are in the state ASP-ACTIVE, the SGP MUST send a Notify message ("AS-Pending") to all of the ASPs in the AS which are in the state ASP-INACTIVE. The SGP SHOULD start buffering the incoming messages for T(r) seconds, after which messages MAY be discarded. T(r) is configurable by the network operator. If the SGP receives an ASP Active message from an ASP in the AS before expiry of T(r), the buffered traffic is directed to that ASP and the timer is cancelled. If T(r) expires, the AS is moved to the AS-INACTIVE state.

#### 4.3.4.4.1 IPSP Considerations (ASP Inactive)

An IPSP may be considered in the ASP-INACTIVE state by a remote IPSP after an ASP Inactive or ASP Inactive Ack message has been received from it.

Alternatively, an interchange of ASP Inactive messages from each end can be performed. This option follows the ASP state transition diagram and gives the additional advantage of selecting a particular AS to be deactivated from each end. It is especially useful when an IPSP is serving more than one AS. It would need four messages for completion.

#### 4.3.4.5 Notify Procedures

A Notify message reflecting a change in the AS state MUST be sent to all ASPs in the AS, except those in the ASP-DOWN state, with appropriate Status Information and any ASP Identifier of the failed ASP. At the ASP, Layer Management is informed with an M-NOTIFY indication primitive. The Notify message must be sent whether the AS state change was a result of an ASP failure or reception of an ASP State management (ASPSM) / ASP Traffic Management (ASPTM) message. In the second case, the Notify message MUST be sent after any related acknowledgement messages (e.g., ASP Up Ack, ASP Down Ack, ASP Active Ack, or ASP Inactive Ack).

In the case where a Notify message ("AS-PENDING") message is sent by an SGP that now has no ASPs active to service the traffic, or where a Notify ("Insufficient ASP resources active in AS") message is sent in the Loadshare or Broadcast mode, the Notify message does not explicitly compel the ASP(s) receiving the message to become active. The ASPs remain in control of what (and when) traffic action is taken.

In the case where a Notify message does not contain a Routing Context parameter, the receiver must know, via configuration data, of which Application Servers the ASP is a member and take the appropriate action in each AS.

#### 4.3.4.5.1 IPSP Considerations (NTFY)

Notify works in the same manner as in the SG-AS case. One of the IPSPs can send this message to any remote IPSP that is not in the ASP-DOWN state.

#### 4.3.4.6 Heartbeat Procedures

The optional Heartbeat procedures MAY be used when operating over transport layers that do not have their own heartbeat mechanism for detecting loss of the transport association (i.e., other than SCTP).

Either M3UA peer may optionally send Heartbeat messages periodically, subject to a provisionable timer  $T(\text{beat})$ . Upon receiving a Heartbeat message, the M3UA peer MUST respond with a Heartbeat Ack message.

If no Heartbeat Ack message (or any other M3UA message) is received from the M3UA peer within  $2 * T(\text{beat})$ , the remote M3UA peer is considered unavailable. Transmission of Heartbeat messages is stopped and the signalling process SHOULD attempt to re-establish communication if it is configured as the client for the disconnected M3UA peer.

The Heartbeat message may optionally contain an opaque Heartbeat Data parameter that MUST be echoed back unchanged in the related Heartbeat Ack message. The sender, upon examining the contents of the returned Heartbeat Ack message, MAY choose to consider the remote M3UA peer as unavailable. The contents/format of the Heartbeat Data parameter is implementation-dependent and only of local interest to the original sender. The contents may be used, for example, to support a Heartbeat sequence algorithm (to detect missing Heartbeats), and/or a timestamp mechanism (to evaluate delays).

Note: Heartbeat related events are not shown in Figure 3 "ASP state transition diagram".

## 4.4 Routing Key Management Procedures [Optional]

### 4.4.1 Registration

An ASP MAY dynamically register with an SGP as an ASP within an Application Server using the REG REQ message. A Routing Key parameter in the REG REQ message specifies the parameters associated with the Routing Key.

The SGP examines the contents of the received Routing Key parameter and compares it with the currently provisioned Routing Keys. If the received Routing Key matches an existing SGP Routing Key entry, and the ASP is not currently included in the list of ASPs for the related Application Server, the SGP MAY authorize the ASP to be added to the AS. Or, if the Routing Key does not currently exist and the received Routing Key data is valid and unique, an SGP supporting dynamic configuration MAY authorize the creation of a new Routing Key and related Application Server and add the ASP to the new AS. In either case, the SGP returns a Registration Response message to the ASP, containing the same Local-RK-Identifier as provided in the initial request, and a Registration Result "Successfully Registered". A unique Routing Context value assigned to the SGP Routing Key is included. The method of Routing Context value assignment at the SGP is implementation dependent but must be guaranteed to be unique for each Application Server or Routing Key supported by the SGP.

If the SGP does not support the registration procedure, the SGP returns an Error message to the ASP, with an error code of "Unsupported Message Type".

If the SGP determines that the received Routing Key data is invalid, or contains invalid parameter values, the SGP returns a Registration Response message to the ASP, containing a Registration Result "Error Invalid Routing Key", "Error - Invalid DPC", "Error - Invalid Network Appearance" as appropriate.

If the SGP determines that a unique Routing Key cannot be created, the SGP returns a Registration Response message to the ASP, with a Registration Status of "Error - Cannot Support Unique Routing". An incoming signalling message received at an SGP should not match against more than one Routing Key.

If the SGP does not authorize an otherwise valid registration request, the SGP returns a REG RSP message to the ASP containing the Registration Result "Error - Permission Denied".

If an SGP determines that a received Routing Key does not currently exist and the SGP does not support dynamic configuration, the SGP returns a Registration Response message to the ASP, containing a Registration Result "Error - Routing Key not Currently Provisioned".

If an SGP determines that a received Routing Key does not currently exist and the SGP supports dynamic configuration but does not have the capacity to add new Routing Key and Application Server entries, the SGP returns a Registration Response message to the ASP, containing a Registration Result "Error - Insufficient Resources".

If an SGP determines that one or more of the Routing Key parameters are not supported for the purpose of creating new Routing Key entries, the SGP returns a Registration Response message to the ASP, containing a Registration Result "Error - Unsupported RK parameter field". This result MAY be used if, for example, the SGP does not support RK Circuit Range Lists in a Routing Key because the SGP does not support ISUP traffic, or does not provide CIC range granularity.

A Registration Response "Error - Unsupported Traffic Handling Mode" is returned if the Routing Key in the REG REQ contains an Traffic Handling Mode that is inconsistent with the presently configured mode for the matching Application Server.

An ASP MAY register multiple Routing Keys at once by including a number of Routing Key parameters in a single REG REQ message. The SGP MAY respond to each registration request in a single REG RSP message, indicating the success or failure result for each Routing Key in a separate Registration Result parameter. Alternatively the SGP MAY respond with multiple REG RSP messages, each with one or more Registration Result parameters. The ASP uses the Local-RK-Identifier parameter to correlate the requests with the responses.

Upon successful registration of an ASP in an AS, the SGP can now send related SS7 Signalling Network Management messaging, if this did not previously start upon the ASP transitioning to state ASP-INACTIVE

#### 4.4.2 Deregistration

An ASP MAY dynamically deregister with an SGP as an ASP within an Application Server using the Dereg REQ message. A Routing Context parameter in the Dereg REQ message specifies which Routing Keys to deregister. An ASP SHOULD move to the ASP-INACTIVE state for an Application Server before attempting to deregister the Routing Key (i.e., deregister after receiving an ASP Inactive Ack). Also, an ASP SHOULD deregister from all Application Servers that it is a member before attempting to move to the ASP-Down state.



The SGP examines the contents of the received Routing Context parameter and validates that the ASP is currently registered in the Application Server(s) related to the included Routing Context(s). If validated, the ASP is deregistered as an ASP in the related Application Server.

The deregistration procedure does not necessarily imply the deletion of Routing Key and Application Server configuration data at the SG. Other ASPs may continue to be associated with the Application Server, in which case the Routing Key data SHOULD NOT be deleted. If a Deregistration results in no more ASPs in an Application Server, an SG MAY delete the Routing Key data.

The SGP acknowledges the deregistration request by returning a DEREG RSP message to the requesting ASP. The result of the deregistration is found in the Deregistration Result parameter, indicating success or failure with cause.

An ASP MAY deregister multiple Routing Contexts at once by including a number of Routing Contexts in a single DEREG REQ message. The SGP MAY respond to each deregistration request in a single DEREG RSP message, indicating the success or failure result for each Routing Context in a separate Deregistration Result parameter.

#### 4.4.3 IPSP Considerations (REG/DEREG)

The Registration/Deregistration procedures work in the IPSP cases in the same way as in AS-SG cases. An IPSP may register an RK in the remote IPSP. An IPSP is responsible for deregistering the RKs that it has registered.

### 4.5 Procedures to Support the Availability or Congestion Status of SS7 Destination

#### 4.5.1 At an SGP

On receiving an MTP-PAUSE, MTP-RESUME or MTP-STATUS indication primitive from the nodal interworking function at an SGP, the SGP M3UA layer will send a corresponding SS7 Signalling Network Management (SSNM) DUNA, DAVA, SCON, or DUPU message (see Section 3.4) to the M3UA peers at concerned ASPs. The M3UA layer must fill in various fields of the SSNM messages consistently with the information received in the primitives.

The SGP M3UA layer determines the set of concerned ASPs to be informed based on the specific SS7 network for which the primitive indication is relevant. In this way, all ASPs configured to

send/receive traffic within a particular network appearance are informed. If the SGP operates within a single SS7 network appearance, then all ASPs are informed.

DUNA, DAVA, SCON, and DRST messages may be sent sequentially and processed at the receiver in the order sent.

Sequencing is not required for the DUPU or DAUD messages, which MAY be sent unsequenced.

#### 4.5.2 At an ASP

##### 4.5.2.1 Single SG Configurations

At an ASP, upon receiving an SS7 Signalling Network Management (SSNM) message from the remote M3UA Peer, the M3UA layer invokes the appropriate primitive indications to the resident M3UA-Users. Local management is informed.

In the case where a local event has caused the unavailability or congestion status of SS7 destinations, the M3UA layer at the ASP SHOULD pass up appropriate indications in the primitives to the M3UA User, as though equivalent SSNM messages were received. For example, the loss of an SCTP association to an SGP may cause the unavailability of a set of SS7 destinations. MTP-PAUSE indication primitives to the M3UA User are appropriate.

##### 4.5.2.2 Multiple SG Configurations

At an ASP, upon receiving a Signalling Network Management message from the remote M3UA Peer, the M3UA layer updates the status of the affected route(s) via the originating SG and determines, whether or not the overall availability or congestion status of the effected destination(s) has changed. If so, the M3UA layer invokes the appropriate primitive indications to the resident M3UA-Users. Local management is informed.

Implementation Note: To accomplish this, the M3UA layer at an ASP maintains the status of routes via the SG, much like an MTP3 layer maintains route-set status.

#### 4.5.3 ASP Auditing

An ASP may optionally initiate an audit procedure to enquire of an SGP the availability and, if the national congestion method with multiple congestion levels and message priorities is used, congestion status of an SS7 destination or set of destinations. A Destination

Audit (DAUD) message is sent from the ASP to the SGP requesting the current availability and congestion status of one or more SS7 Destination Point Codes.

The DAUD message MAY be sent unsequenced. The DAUD MAY be sent by the ASP in the following cases:

- Periodic. A Timer originally set upon reception of a DUNA, SCON or DRST message has expired without a subsequent DAVA, DUNA, SCON or DRST message updating the availability/congestion status of the affected Destination Point Codes. The Timer is reset upon issuing a DAUD. In this case the DAUD is sent to the SGP that originally sent the SSNM message.
- Isolation. The ASP is newly ASP-ACTIVE or has been isolated from an SGP for an extended period. The ASP MAY request the availability/congestion status of one or more SS7 destinations to which it expects to communicate.

IMPLEMENTATION NOTE: In the first of the cases above, the auditing procedure must not be invoked for the case of a received SCON message containing a congestion level value of "no congestion" or undefined" (i.e., congestion Level = "0"). This is because the value indicates either congestion abatement or that the ITU MTP3 international congestion method is being used. In the international congestion method, the MTP3 layer at the SGP does not maintain the congestion status of any destinations and therefore the SGP cannot provide any congestion information in response to the DAUD. For the same reason, in the second of the cases above a DAUD message cannot reveal any congested destination(s).

The SGP SHOULD respond to a DAUD message with the MTP3 availability/congested status of the routeset associated with each Destination Point Code(s) in the DAUD message. The status of each SS7 destination requested is indicated in a DUNA message (if unavailable), a DAVA message (if available), or a DRST (if restricted and the SGP supports this feature). Where the SGP maintains the congestion status of the SS7 destination, and the SS7 destination is congested, the SGP MUST additionally respond with an SCON message before the DAVA or DRST message. If the SS7 destination is available and congested, the SGP MUST respond with an SCON message and then a DAVA message. If the SS7 destination is restricted and congested, the SGP MUST respond with an SCON message immediately followed by a DRST message. If the SGP has no information on the availability

status of the SS7 destination, the SGP responds with a DUNA message, as it has no routing information to allow it to route traffic to this destination.

Any DUNA or DAVA message in response to a DAUD message MAY contain a list of Affected Point Codes.

An SG MAY refuse to provide the availability or congestion status of a destination if, for example, the ASP is not authorized to know the status of the destination. The SG MAY respond with an Error Message (Error Code = "Destination Status Unknown")

#### 4.6 MTP3 Restart

In the case where the MTP3 in the SG undergoes an MTP restart, event communication SHOULD be handled as follows:

When the SG discovers SS7 network isolation, the SGPs send an indication to all concerned available ASPs (i.e., ASPs in the ASP-ACTIVE state) using DUNA messages for the concerned destinations.

When the SG has completed the MTP Restart procedure, the M3UA layers at the SGPs inform all concerned ASPs in the ASP-ACTIVE state of any available/restricted SS7 destinations using the DAVA/DRST messages. No message is necessary for those destinations still unavailable after the restart procedure.

When the M3UA layer at an ASP receives a DUNA message indicating SS7 destination unavailability at an SG, MTP Users will receive an MTP-PAUSE indication and will stop any affected traffic to this destination. When the M3UA receives a DAVA/DRST message, MTP Users will receive an MTP-RESUME indication and can resume traffic to the newly available SS7 destination, provided the ASP is in the ASP-ACTIVE state towards this SGP.

The ASP MAY choose to audit the availability of unavailable destinations by sending DAUD messages. This would be for example the case when an AS becomes active at an ASP and does not have current destination statuses. If MTP restart is in progress at the SG, the SGP returns a DUNA message for that destination, even if it received an indication that the destination became available or restricted.

In the IPSP case, MTP restart could be considered if the IPSP also has connection to an SS7 network. In that case, the same behavior as described above for the SGP would apply to the restarting IPSP. This would also be the case if the IPSPs were perceived as exchanging MTP Peer PDUs, instead of MTP primitives between MTP User and MTP Provider. In other words, M3UA does not provide the equivalent to

Traffic Restart Allowed messages indicating the end of the restart procedure between peer IPSPs that would also be connected to an SS7 network.

## 5. Examples of M3UA Procedures

NOTE: Not all the Notify messages that are appropriate per the Notify procedures are shown in these examples.


### 5.1 Establishment of Association and Traffic between SGPs and ASPs

These scenarios show the example M3UA message flows for the establishment of traffic between an SGP and an ASP or between two IPSPs. In all cases it is assumed that the SCTP association is already set up.

#### 5.1.1 Single ASP in an Application Server ("1+0" sparing),

These scenarios show the example M3UA message flows for the establishment of traffic between an SGP and an ASP where only one ASP is configured within an AS (no backup).


##### 5.1.1.1 Single ASP in an Application Server ("1+0" sparing), No Registration



Note: If the ASP Active message contains an optional Routing Context parameter, the ASP Active message only applies for the specified RC value(s). For an unknown RC value, the SGP responds with an Error message.


#### 5.1.1.2 Single ASP in Application Server ("1+0" sparing), Dynamic Registration

This scenario is the same as for 5.1.1.1 but with the optional exchange of registration information. In this case the Registration is accepted by the SGP.



Note: In the case of an unsuccessful registration attempt (e.g., invalid RKn), the Register Response message will contain an unsuccessful indication and the ASP will not subsequently send an ASP Active message.


### 5.1.1.3 Single ASP in Multiple Application Servers (each with "1+0" sparing), Dynamic Registration (Case 1 - Multiple Registration Requests)



Note: In the case of an unsuccessful registration attempt (e.g., invalid RKn), the Register Response message will contain an unsuccessful indication and the ASP will not subsequently send an ASP Active message. Each LRC/RK pair registration is considered independently.

It is not necessary to follow a Registration Request/Response message pair with an ASP Active message before sending the next Registration Request. The ASP Active message can be sent at any time after the related successful registration.

#### 5.1.1.4 Single ASP in Multiple Application Servers (each with "1+0" sparing), Dynamic Registration (Case 2 - Single Registration Request)



Note: In the case of an unsuccessful registration attempt (e.g., Invalid RK<sub>n</sub>), the Register Response message will contain an unsuccessful indication and the ASP will not subsequently send an ASP Active message. Each LRC/RK pair registration is considered independently.


The ASP Active message can be sent at any time after the related successful registration, and may have more than one RC.

#### 5.1.2 Two ASPs in Application Server ("1+1" sparing)

This scenario shows the example M3UA message flows for the establishment of traffic between an SGP and two ASPs in the same Application Server, where ASP1 is configured to be in the ASP-ACTIVE state and ASP2 is to be a "backup" in the event of communication failure or the withdrawal from service of ASP1. ASP2 may act as a hot, warm, or cold backup depending on the extent to which ASP1 and ASP2 share call/transaction state or can communicate call state under failure/withdrawal events. The example message flow is the same




whether the ASP Active messages indicate "Override", "Loadshare" or "Broadcast" mode, although typically this example would use an Override mode.




#### 5.1.3 Two ASPs in an Application Server ("1+1" sparing, loadsharing case)

This scenario shows a similar case to Section 5.1.2 but where the two ASPs are brought to the state ASP-ACTIVE and subsequently loadshare the traffic. In this case, one ASP is sufficient to handle the total traffic load.



#### 5.1.4 Three ASPs in an Application Server ("n+k" sparing, loadsharing case)


This scenario shows the example M3UA message flows for the establishment of traffic between an SGP and three ASPs in the same Application Server, where two of the ASPs are brought to the state ASP-ACTIVE and subsequently share the load. In this case, a minimum of two ASPs are required to handle the total traffic load (2+1 sparing).



## 5.2 ASP Traffic Failover Examples

### 5.2.1 (1+1 Sparing, Withdrawal of ASP, Backup Override)


Following on from the example in Section 5.1.2, and ASP1 withdraws from service:



Note: If the SGP M3UA layer detects the loss of the M3UA peer (e.g., M3UA heartbeat loss or detection of SCTP failure), the initial ASP Inactive message exchange (i.e., SGP to ASP1) would not occur.


### 5.2.2 (1+1 Sparing, Backup Override)

Following on from the example in Section 5.1.2, ASP2 wishes to Override ASP1 and take over the traffic:



### 5.2.3 (n+k Sparing, Loadsharing case, Withdrawal of ASP)

Following on from the example in Section 5.1.4, and ASP1 withdraws from service:




For the Notify message to be sent, the SG maintains knowledge of the minimum ASP resources required (e.g., if the SG knows that "n+k" = "2+1" for a Loadshare AS and "n" currently equals "1").

Note: If the SGP detects loss of the ASP1 M3UA peer (e.g., M3UA heartbeat loss or detection of SCTP failure), the initial ASP Inactive message exchange (i.e., SGP-ASP1) would not occur.

### 5.3 Normal Withdrawal of an ASP from an Application Server and Teardown of an Association

An ASP which is now confirmed in the state ASP-INACTIVE (i.e., the ASP has received an ASP Inactive Ack message) may now proceed to the ASP-DOWN state, if it is to be removed from service. Following on from Section 5.2.1 or 5.2.3, where ASP1 has moved to the "Inactive" state:



Note: The Deregistration procedure will typically be used if the ASP previously used the Registration procedures for configuration within the Application Server. ASP Inactive and Deregister messages exchanges may contain multiple Routing Contexts.

The ASP should be in the ASP-INACTIVE state and should have deregistered in all its Routing Contexts before attempting to move to the ASP-DOWN state.

## 5.4 M3UA/MTP3-User Boundary Examples

### 5.4.1 At an ASP

This section describes the primitive mapping between the MTP3 User and the M3UA layer at an ASP.


#### 5.4.1.1 Support for MTP-TRANSFER Primitives at the ASP

##### 5.4.1.1.1 Support for MTP-TRANSFER Request Primitive

When the MTP3-User on the ASP has data to send to a remote MTP3-User, it uses the MTP-TRANSFER request primitive. The M3UA layer at the ASP will do the following when it receives an MTP-TRANSFER request primitive from the M3UA user:

- Determine the correct SGP;
- Determine the correct association to the chosen SGP;
- Determine the correct stream in the association (e.g., based on SLS);


- Determine whether to complete the optional fields of the DATA message;
- Map the MTP-TRANSFER request primitive into the Protocol Data field of a DATA message;
- Send the DATA message to the remote M3UA peer at the SGP, over the SCTP association.



#### 5.4.1.1.2 Support for the MTP-TRANSFER Indication Primitive


When the M3UA layer on the ASP receives a DATA message from the M3UA peer at the remote SGP, it will do the following:

- Evaluate the optional fields of the DATA message, if present;
- Map the Protocol Data field of a DATA message into the MTP-TRANSFER indication primitive;
- Pass the MTP-TRANSFER indication primitive to the user part. In case of multiple user parts, the optional fields of the Data message are used to determine the concerned user part.



#### 5.4.1.1.3 Support for ASP Querying of SS7 Destination States

There are situations such as temporary loss of connectivity to the SGP that may cause the M3UA layer at the ASP to audit SS7 destination availability/congestion states. Note: there is no primitive for the MTP3-User to request this audit from the M3UA layer as this is initiated by an internal M3UA management function.




#### 5.4.2 At an SGP

This section describes the primitive mapping between the MTP3-User and the M3UA layer at an SGP.

##### 5.4.2.1 Support for MTP-TRANSFER Request Primitive at the SGP

When the M3UA layer at the SGP has received DATA messages from its peer destined to the SS7 network it will do the following:

- Evaluate the optional fields of the DATA message, if present, to determine the Network Appearance;
- Map the Protocol data field of the DATA message into an MTP-TRANSFER request primitive;
- Pass the MTP-TRANSFER request primitive to the MTP3 of the concerned Network Appearance.



##### 5.4.2.2 Support for MTP-TRANSFER Indication Primitive at the SGP

When the MTP3 layer at the SGP has data to pass its user parts, it will use the MTP-TRANSFER indication primitive. The M3UA layer at the SGP will do the following when it receives an MTP-TRANSFER indication primitive:

- Determine the correct AS using the distribution function;
- Select an ASP in the ASP-ACTIVE state
- Determine the correct association to the chosen ASP;
- Determine the correct stream in the SCTP association (e.g., based on SLS);

- Determine whether to complete the optional fields of the DATA message;
- Map the MTP-TRANSFER indication primitive into the Protocol Data field of a DATA message;
- Send the DATA message to the remote M3UA peer in the ASP, over the SCTP association




#### 5.4.2.3 Support for MTP-PAUSE, MTP-RESUME, MTP-STATUS Indication Primitives

The MTP-PAUSE, MTP-RESUME and MTP-STATUS indication primitives from the MTP3 upper layer interface at the SGP need to be made available to the remote MTP3 User Part lower layer interface at the concerned ASP(s).

##### 5.4.2.3.1 Destination Unavailable


The MTP3 layer at the SGP will generate an MTP-PAUSE indication primitive when it determines locally that an SS7 destination is unreachable. The M3UA layer will map this primitive to a DUNA message. The SGP M3UA layer determines the set of concerned ASPs to be informed based on internal SS7 network information associated with the MTP-PAUSE indication primitive indication.



##### 5.4.2.3.2 Destination Available


The MTP3 at the SGP will generate an MTP-RESUME indication primitive when it determines locally that an SS7 destination that was previously unreachable is now reachable. The M3UA layer will map this primitive to a DAVA message. The SGP M3UA determines the set of concerned ASPs to be informed based on internal SS7 network information associated with the MTP-RESUME indication primitive.






#### 5.4.2.3.3 SS7 Network Congestion

The MTP3 layer at the SGP will generate an MTP-STATUS indication primitive when it determines locally that the route to an SS7 destination is congested. The M3UA layer will map this primitive to a SCON message. It will determine which ASP(s) to send the SCON message to, based on the intended Application Server.



#### 5.4.2.3.4 Destination User Part Unavailable


The MTP3 layer at the SGP will generate an MTP-STATUS indication primitive when it receives an UPU message from the SS7 network. The M3UA layer will map this primitive to a DUPU message. It will determine which ASP(s) to send the DUPU based on the intended Application Server.



### 5.5 Examples for IPSP communication.


These scenarios show a basic example for IPSP communication for the three phases of the connection (establishment, data exchange, disconnection). It is assumed that the SCTP association is already set up. Both single exchange and double exchange behavior are included for illustrative purposes.

## 5.5.1 Single exchange:



Routing Context are previously agreed to be the same in both directions.

## 5.5.2 Double exchange:



In this approach, only one single exchange of ASP Up message can be considered as enough since the response by the other peer can be considered as a notice that it is in ASP\_UP state.

For the same reason, only one ASP Down message is needed since once that an IPSP receives ASP\_Down ack message it is itself considered as being in the ASP\_Down state and not allowed to receive ASPSM messages.

## 6. Security Considerations

### 6.1 Introduction

M3UA is designed to carry signalling messages for telephony services. As such, M3UA must involve the security needs of several parties: the end users of the services; the network providers and the applications involved. Additional requirements may come from local regulation. While having some overlapping security needs, any security solution should fulfill all of the different parties' needs.

### 6.2 Threats

There is no quick fix, one-size-fits-all solution for security. As a transport protocol, M3UA has the following security objectives:

- \* Availability of reliable and timely user data transport.
- \* Integrity of user data transport.
- \* Confidentiality of user data.

M3UA is recommended to be transported on SCTP. SCTP [17] provides certain transport related security features, such as some protection against:

- \* Blind Denial of Service Attacks
- \* Flooding
- \* Masquerade
- \* Improper Monopolization of Services

When M3UA is running in professionally managed corporate or service provider network, it is reasonable to expect that this network includes an appropriate security policy framework. The "Site Security Handbook" [22] should be consulted for guidance.

When the network in which M3UA runs in involves more than one party, it may not be reasonable to expect that all parties have implemented security in a sufficient manner. In such a case, it is recommended that IPSEC is used to ensure confidentiality of user payload. Consult [23] for more information on configuring IPSEC services.

### 6.3 Protecting Confidentiality

Particularly for mobile users, the requirement for confidentiality may include the masking of IP addresses and ports. In this case application level encryption is not sufficient; IPSEC ESP [24] SHOULD be used instead. Regardless of which level performs the encryption, the IPSEC ISAKMP [25] service SHOULD be used for key management.

## 7. IANA Considerations

### 7.1 SCTP Payload Protocol Identifier

IANA has assigned an M3UA value for the Payload Protocol Identifier in the SCTP DATA chunk. The following SCTP Payload Protocol Identifier is registered:

M3UA      "3"

The SCTP Payload Protocol Identifier value "3" SHOULD be included in each SCTP DATA chunk, to indicate that the SCTP is carrying the M3UA protocol. The value "0" (unspecified) is also allowed but any other values MUST not be used. This Payload Protocol Identifier is not directly used by SCTP but MAY be used by certain network entities to identify the type of information being carried in a DATA chunk.

The User Adaptation peer MAY use the Payload Protocol Identifier as a way of determining additional information about the data being presented to it by SCTP.

### 7.2 M3UA Port Number

IANA has registered SCTP (and UDP/TCP) Port Number 2905 for M3UA. It is recommended that SGPs use this SCTP port number for listening for new connections. SGPs MAY also use statically configured SCTP port numbers instead.

### 7.3 M3UA Protocol Extensions

This protocol may also be extended through IANA in three ways:

- through definition of additional message classes,
- through definition of additional message types, and
- through definition of additional message parameters

The definition and use of new message classes, types and parameters is an integral part of SIGTRAN adaptation layers. Thus these extensions are assigned by IANA through an IETF Consensus action as defined in Guidelines for Writing an IANA Considerations Section in RFCs [25]

The proposed extension must in no way adversely affect the general working of the protocol.

### 7.3.1 IETF Defined Message Classes

The documentation for a new message class MUST include the following information:

- (a) A long and short name for the new message class;
- (b) A detailed description of the purpose of the message class.

### 7.3.2 IETF Defined Message Types

The documentation for a new message type MUST include the following information:

- (a) A long and short name for the new message type;
- (b) A detailed description of the structure of the message;
- (c) A detailed definition and description of intended use for each field within the message;
- (d) A detailed procedural description of the use of the new message type within the operation of the protocol;
- (e) A detailed description of error conditions when receiving this message type.

When an implementation receives a message type which it does not support, it MUST respond with an Error (ERR) message ("Unsupported Message Type").

### 7.3.3 IETF Defined Parameter Extension

Documentation of the message parameter MUST contain the following information:

- (a) Name of the parameter type;
- (b) Detailed description of the structure of the parameter field. This structure MUST conform to the general type-length-value format described in Section 3.2;
- (c) Detailed definition of each component of the parameter value;
- (d) Detailed description of the intended use of this parameter type, and an indication of whether and under what circumstances multiple instances of this parameter type may be found within the same message.

## 8. References

### 8.1 Normative References

- [1] ITU-T Recommendations Q.761 to Q.767, "Signalling System No.7 (SS7) - ISDN User Part (ISUP)"
- [2] ANSI T1.113 - "Signaling System Number 7 - ISDN User Part"
- [3] ETSI ETS 300 356-1 "Integrated Services Digital Network (ISDN); Signalling System No.7; ISDN User Part (ISUP) version 2 for the international interface; Part 1: Basic services"
- [4] ITU-T Recommendations Q.711 to Q.715, "Signalling System No. 7 (SS7) - Signalling Connection Control Part (SCCP)"
- [5] ANSI T1.112 "Signaling System Number 7 - Signaling Connection Control Part"
- [6] ETSI ETS 300 009-1, "Integrated Services Digital Network (ISDN); Signalling System No.7; Signalling Connection Control Part (SCCP) (connectionless and connection-oriented class 2) to support international interconnection; Part 1: Protocol specification"
- [7] ITU-T Recommendations Q.701 to Q.705, "Signalling System No. 7 (SS7) - Message Transfer Part (MTP)"
- [8] ANSI T1.111 "Signaling System Number 7 - Message Transfer Part"
- [9] ETSI ETS 300 008-1, "Integrated Services Digital Network (ISDN); Signalling System No.7; Message Transfer Part (MTP) to support international interconnection; Part 1: Protocol specification"
- [10] Yergeau, F., "UTF-8, a transformation format of ISO 10646", RFC 2279, January 1998.

### 8.2 Informative References

- [11] Ong, L., Rytina, M., Garcia, H., Schwarzbauer, L., Coene, H., Lin, I., Juhasz, M. and C. Holdrege, "Framework Architecture for Signaling Transport", RFC 2719, October 1999.
- [12] ITU-T Recommendation Q.720, "Telephone User Part"

- [13] ITU-T Recommendations Q.771 to Q.775 "Signalling System No. 7 (SS7) - Transaction Capabilities (TCAP)"
- [14] ANSI T1.114 "Signaling System Number 7 - Transaction Capabilities Application Part"
- [15] ETSI ETS 300 287-1, "Integrated Services Digital Network (ISDN); Signalling System No.7; Transaction Capabilities (TC) version 2; Part 1: Protocol specification"
- [16] 3G TS 25.410 V4.0.0 (2001-04) "Technical Specification - 3rd Generation partnership Project; Technical Specification Group Radio Access Network; UTRAN Iu Interface: General Aspects and Principles"
- [17] Stewart, R., Xie, Q., Mornmeault, K., Sharp, H., Taylor, T., Rytina, I., Kalla, M., Zhang, L. and V. Paxson, "Stream Control Transport Protocol", RFC 2960, October 2000.
- [18] ITU-T Recommendation Q.2140 "B-ISDN ATM Adaptation Layer - Service Specific Coordination Function for signalling at the Network Node Interface (SSCF at NNI)"
- [19] ITU-T Recommendation Q.2110 "B-ISDN ATM Adaptation Layer - Service Specific Connection Oriented Protocol (SSCOP)"
- [20] Bradner, S., "Key words for use in RFCs to Indicate Requirement Levels", BCP 14, RFC 2119, March 1997.
- [21] ITU-T Recommendation Q.2210 "Message Transfer Part Level 3 functions and messages using the services of ITU Recommendation Q.2140"
- [22] Fraser, B., "Site Security Handbook", FYI 8, RFC 2196, September 1997.
- [23] Ramakrishnan, S., Floyd, S. and D. Black, "Security Architecture for the Internet Protocol", RFC 3168, November 1998.
- [24] Kent, S. and R. Atkinson, "IP Encapsulating Security Payload (ESP)", RFC 2406, November 1998.
- [25] Maughan, D., Schertler, M., Schneider, M. and J. Turner, "Internet Security Association and Key Management Protocol", RFC 2408, November 1998.
- [26] Narten, T. and H. Alverstrand, "Guidelines for Writing an IANA Considerations Section in RFCs", BCP 26, RFC 2434, October 1998.



- [27] Morneault, K., Dantu, R., Sidebottom, G., Bidulock, B. and J. Heitz, "Signaling System 7 (SS7) Message Transfer Part 2 (MTP2) - User Adaptation Layer", RFC 3331, August 2002.
- [28] George, T., et. al., "SS7 MTP2-User Peer-to-Peer Adaptation Layer", Work in Progress.
- [29] Telecommunication Technology Committee (TTC) Standard JT-Q704, "Message Transfer Part Signaling Network Functions", April 28, 1992.

## 9. Acknowledgements

The authors would like to thank Antonio Roque Alvarez, Joyce Archibald, Tolga Asveren, Maria-Cruz Bartolome-Rodrigo, Dan Brendes, Antonio Caete, Nikhil Jain, Roland Jesske, Joe Keller, Kurt Kite, Ming Lin, Steve Lorusso, Naoto Makinae, Howard May, Francois Mouillaud, Barry Nagelberg, Neil Olson, Heinz Prantner, Shyamal Prasad, Mukesh Punhani, Selvam Rengasami, John Schantz, Ray Singh, Michael Tuexen, Nitin Tomar, Gery Verwimp, Tim Vetter, Kazuo Watanabe, Ben Wilson and many others for their valuable comments and suggestions.

## 10. Document Contributors

Ian Rytina - Ericsson  
Guy Mousseau - Nortel Networks  
Lyndon Ong - Ciena  
Hanns Juergen Schwarzbauer - Siemens  
Klaus Gradischnig - Detecon Inc.  
Mallesh Kalla - Telcordia  
Normand Glaude - Performance Technologies  
Brian Bidulock - OpenSS7  
John Loughney - Nokia


## Appendix A

### A.1 Signalling Network Architecture

A Signalling Gateway is used to support the transport of MTP3-User signalling traffic received from the SS7 network to multiple distributed ASPs (e.g., MGCs and IP Databases). Clearly, the M3UA protocol is not designed to meet the performance and reliability requirements for such transport by itself. However, the conjunction of distributed architecture and redundant networks provides support for reliable transport of signalling traffic over IP. The M3UA protocol is flexible enough to allow its operation and management in a variety of physical configurations, enabling Network Operators to meet their performance and reliability requirements.

To meet the stringent SS7 signalling reliability and performance requirements for carrier grade networks, Network Operators might require that no single point of failure is present in the end-to-end network architecture between an SS7 node and an IP-based application. This can typically be achieved through the use of redundant SGPs or SGs, redundant hosts, and the provision of redundant QOS-bounded IP network paths for SCTP Associations between SCTP End Points. Obviously, the reliability of the SG, the MGC and other IP-based functional elements also needs to be taken into account. The distribution of ASPs and SGPs within the available Hosts MAY also be considered. As an example, for a particular Application Server, the related ASPs could be distributed over at least two Hosts.

One example of a physical network architecture relevant to SS7 carrier grade operation in the IP network domain is shown in Figure 5 below:



SGP1.1 and SGP1.2 are part of SG1  
 SGP2.1 and SGP2.2 are part of SG2

Figure 5 - Physical Model

In this model, each host may have many application processes. In the case of the MGC, an ASP may provide service to one or more Application Servers, and is identified as an SCTP end point. One or more Signalling Gateway Processes make up a single Signalling Gateway.

This example model can also be applied to IPSP-IPSP signalling. In this case, each IPSP may have its services distributed across 2 hosts or more, and may have multiple server processes on each host.

In the example above, each signalling process (SGP, ASP or IPSP) is the end point to more than one SCTP association, leading to more than one other signalling processes. To support this, a signalling process must be able to support distribution of M3UA messages to many simultaneous active associations. This message distribution function is based on the status of provisioned Routing Keys, the status of the signalling routes to signalling points in the SS7 network, and the redundancy model (active-standby, load sharing, broadcast, n+k) of the remote signalling processes.

For carrier grade networks, the failure or isolation of a particular signalling process should not cause stable calls or transactions to be lost. This implies that signalling processes need, in some cases, to share the call/transaction state or be able to pass the call state information between each other. In the case of ASPs performing call processing, coordination may also be required with the related Media Gateway to transfer the MGC control for a particular trunk termination. However, this sharing or communication of call/transaction state information is outside the scope of this document.

This model serves as an example. M3UA imposes no restrictions as to the exact layout of the network elements, the message distribution algorithms and the distribution of the signalling processes. Instead, it provides a framework and a set of messages that allow for a flexible and scalable signalling network architecture, aiming to provide reliability and performance.

## A.2 Redundancy Models

### A.2.1 Application Server Redundancy

At the SGP, an Application Server list contains active and inactive ASPs to support ASP broadcast, loadsharing and failover procedures. The list of ASPs within a logical Application Server is kept updated in the SGP to reflect the active Application Server Process(es).

For example, in the network shown in Figure 1, all messages to DPC x could be sent to ASP1 in Host3 or ASP1 in Host4. The AS list at SGP1 in Host 1 might look like the following:

```
Routing Key {DPC=x} - "Application Server #1"
  ASP1/Host3 - State = Active
  ASP1/Host4 - State = Inactive
```

In this "1+1" redundancy case, ASP1 in Host3 would be sent any incoming message with DPC=x. ASP1 in Host4 would normally be brought to the "active" state upon failure of, or loss of connectivity to, ASP1/Host1.

The AS List at SGP1 in Host1 might also be set up in loadshare mode:

```
Routing Key {DPC=x} - "Application Server #1"
  ASP1/Host3 - State = Active
  ASP1/Host4 - State = Active
```

In this case, both the ASPs would be sent a portion of the traffic. For example the two ASPs could together form a database, where incoming queries may be sent to any active ASP.

Care might need to be exercised by a Network Operator in the selection of the routing information to be used as the Routing Key for a particular AS.

For example, where Application Servers are defined using ranges of ISUP CIC values, the Operator is implicitly splitting up control of the related circuit groups. Some CIC value range assignments may interfere with ISUP circuit group management procedures.

In the process of failover, it is recommended that in the case of ASPs supporting call processing, stable calls do not fail. It is possible that calls in "transition" may fail, although measures of communication between the ASPs involved can be used to mitigate this. For example, the two ASPs may share call state via shared memory, or

may use an ASP to ASP protocol to pass call state information. Any ASP-to-ASP protocol to support this function is outside the scope of this document.

#### A.2.2 Signalling Gateway Redundancy

Signalling Gateways may also be distributed over multiple hosts. Much like the AS model, SGs may comprise one or more SG Processes (SGPs), distributed over one or more hosts, using an active/backup or a loadsharing model. Should an SGP lose all or partial SS7 connectivity and other SGPs exist, the SGP may terminate the SCTP associations to the concerned ASPs.

It is therefore possible for an ASP to route signalling messages destined to the SS7 network using more than one SGP. In this model, a Signalling Gateway is deployed as a cluster of hosts acting as a single SG. A primary/backup redundancy model is possible, where the unavailability of the SCTP association to a primary SGP could be used to reroute affected traffic to an alternate SGP. A loadsharing model is possible, where the signalling messages are loadshared between multiple SGPs. A broadcast model is also possible, where signalling messages are sent to each active SGP in the SG. The distribution of the MTP3-user messages over the SGPs should be done in such a way to minimize message missequencing, as required by the SS7 User Parts.

It may also be possible for an ASP to use more than one SG to access a specific SS7 end point, in a model that resembles an SS7 STP mated pair. Typically, SS7 STPs are deployed in mated pairs, with traffic loadshared between them. Other models are also possible, subject to the limitations of the local SS7 network provisioning guidelines.

From the perspective of the M3UA layer at an ASP, a particular SG is capable of transferring traffic to a provisioned SS7 destination X if an SCTP association with at least one SGP of the SG is established, the SGP has returned an acknowledgement to the ASP to indicate that the ASP is actively handling traffic for that destination X, the SGP has not indicated that the destination X is inaccessible and the SGP has not indicated MTP Restart. When an ASP is configured to use multiple SGPs for transferring traffic to the SS7 network, the ASP must maintain knowledge of the current capability of the SGPs to

handle traffic to destinations of interest. This information is crucial to the overall reliability of the service, for active/backup, loadsharing and broadcast models, in the event of failures, recovery and maintenance activities. The ASP M3UA may also use this information for congestion avoidance purposes. The distribution of the MTP3-user messages over the SGPs should be done in such a way to minimize message missequencing, as required by the SS7 User Parts.

## Editors' Addresses

Greg Sidebottom  
Signatus Technologies  
Kanata, Ontario, Canada

EMail: greg@signatustechnologies.com

Ken Morneault  
Cisco Systems Inc.  
13615 Dulles Technology Drive  
Herndon, VA, USA 20171

EMail: kmorneau@cisco.com

Javier Pastor-Balbas  
Ericsson Espana S.A.  
C/ Retama 1  
28045 Madrid - Spain

EMail: j.javier.pastor@ericsson.com

## Full Copyright Statement

Copyright (C) The Internet Society (2002). All Rights Reserved.

This document and translations of it may be copied and furnished to others, and derivative works that comment on or otherwise explain it or assist in its implementation may be prepared, copied, published and distributed, in whole or in part, without restriction of any kind, provided that the above copyright notice and this paragraph are included on all such copies and derivative works. However, this document itself may not be modified in any way, such as by removing the copyright notice or references to the Internet Society or other Internet organizations, except as needed for the purpose of developing Internet standards in which case the procedures for copyrights defined in the Internet Standards process must be followed, or as required to translate it into languages other than English.

The limited permissions granted above are perpetual and will not be revoked by the Internet Society or its successors or assigns.

This document and the information contained herein is provided on an "AS IS" basis and THE INTERNET SOCIETY AND THE INTERNET ENGINEERING TASK FORCE DISCLAIMS ALL WARRANTIES, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO ANY WARRANTY THAT THE USE OF THE INFORMATION HEREIN WILL NOT INFRINGE ANY RIGHTS OR ANY IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE.

## Acknowledgement

Funding for the RFC Editor function is currently provided by the Internet Society.



